

# Horizon Data-va Service Command Line Interface

Horizon Workspace1.8

EN-001321-00

**vmware**<sup>®</sup>

You can find the most up-to-date documentation on the VMware Web site at <http://www.vmware.com/support/>

Copyright © 2013-2014 VMware, Inc. All rights reserved. [Copyright and trademark information.](#)

**VMware, Inc.**  
3401 Hillview Avenue  
Palo Alto, CA 94304  
[www.vmware.com](http://www.vmware.com)

# Content

Horizon Data-va Service CLI Utility Overview .....	5
Intended Audience .....	5
General Tool Information .....	5
Attribute File .....	6
Running CLIs .....	6
Horizon Data-va Service CLI Commands .....	7
Using non-ASCII Characters in CLIs .....	8
Provisioning (zmprov) .....	8
Managing Guest Users' Class of Service .....	10
Changing SMTP Server Settings .....	11
Other Types of zmprov Commands .....	12
Start/Stop/Restart Service on the Data-va (zmcontrol) .....	12
Move Accounts from One Data-va to Another (zmmboxmove) .....	13
Check Account Move Status (zmmboxmovequery) .....	14
Purge the Old Account After a Move (zmpurgeoldmbox) .....	14
Data-va Local Configuration Options (zmlocalconfig) .....	15
Data Store Account Management (zmmailbox) .....	16
Metadata Dump (zmmetadump) .....	17
SOAP Format (zmsoap) .....	17
Thread Dump (zmthrdump) .....	19
Manage Data Store Storage Volumes (zmvolume) .....	19
Index Volumes .....	19
Files Volumes .....	20



# Horizon Data-va Service CLI Utility Overview

---

The command line interface (CLI) tool for the VMware Horizon Workspace Server data-va virtual machine lets you run system administration commands to manage users' data stores. The Horizon Workspace Administrator Web Client interface is the main tool for maintaining the Horizon Workspace, but some data-va services can only be changed from the CLI utility.

## Intended Audience

This information is written for experienced Windows or Linux system administrators who are familiar with virtual machine technology and know how to use commands in scripts.

## General Tool Information

The data-va service CLI tool follows standard UNIX command-line conventions.

Follow these guidelines when using the commands:

- CLI commands are run as the zimbra user, that is **su - zimbra**.
- The actual CLI commands are case-sensitive. You must type them in lower case.
- Press **ENTER** after you type a command.
- Typing the CLI command and then **-h** displays the usage options for the command. Example: **zmprov -h** lists all the options available for the zmprov utility.
- Each operation is invoked through command-line options. Many have a long name and a short name. For example, these two commands are equivalent:

```
zmprov modifyAccount joe@domain.com test123
```

```
zmprov ma joe@domain.com test123
```

## Syntax Conventions

When demonstrating the syntax of each tool, the following conventions indicate required, optional, and alternate values:

- {attribute} in curly brackets is required information.
- [attribute] in square brackets are optional arguments or information.
- {a|b|c} or [a|b|c] options separated by the pipe character | means "a" OR "b" OR "c"
- For attribute names that contain spaces, surround the name with double quotes.

## Attribute File

The list of attributes that can be set and their descriptions is in the `/opt/zimbra/bin` directory on the `data-va` virtual machine.

To quickly see this list, as a `zimbra` user type

```
zmprov describe
```

## Running CLIs

The CLI commands are run directly on the Horizon Files `data-va` virtual machine.

1. Log on to the vSphere Client and select the `data-va`.
2. Select the Console tab and click **Enter**.
3. To login, type  
**root**
4. Enter the password you set as the global root password on the `configurator-va`.
5. All Files CLI commands should be run as the `zimbra` user. Switch user from `root`, type  
**su - zimbra**

# Horizon Data-va Service CLI Commands

---

The table below lists the CLI commands used for data-va services. The list of CLIs that can be used is located in the `/opt/zimbra/bin` directory on data-va virtual machines.

## List of CLI Commands for Horizon Files Service

CLI	Description
<code>ldap</code>	Start, stop, or find the status of Horizon Files LDAP
<code>ldapsearch</code>	Perform a search on the Horizon Files LDAP server
<code>mysql</code>	Enters interactive command-line MySQL session with the data-va service's mysql
<code>mysql.server</code>	Start, stop the SQL instance for the data-va package
<code>mysqladmin</code>	Send admin commands to MySQL
<code>zmcontrol</code>	Start, stop, restart, status of the data-va virtual machine
<code>zmdumpenv</code>	General information about the data-va virtual machine environment is displayed
<code>zmhostname</code>	Find the hostname of the data-va virtual machine
<code>zmlocalconfig</code>	Used to set or get the local configuration of a data-va virtual machine
<code>zmmailbox</code>	Performs data store management tasks
<code>zmmailboxctl</code>	Start, stop, reload, or find the status of the data-va virtual machine (mailboxd)
<code>zmmboxmove</code>	Used to move selected users' data store from one data-va virtual machine to another
<code>zmmboxmovequery</code>	Used to query ongoing data store moves on a server
<code>zmpurgeoldmbox</code>	Purges a data store from the old server after a data store move
<code>zmmetadump</code>	Support tool that dumps an item's metadata in a human-readable form

## List of CLI Commands for Horizon Files Service

CLI	Description
<b>zmmysqlstatus</b>	Status of folder MySQL instance
<b>zmprov</b>	Performs all provisioning tasks in the Horizon Files LDAP, including modifying account and Class of Service attributes
<b>zmpython</b>	Ability to write Python scripts that access data-va services Java libraries. It sets the class path and starts the Jython interpreter.
<b>zmsoap</b>	SOAP calls can be made that can either modify the data-va settings, COS or account settings
<b>zmthrdump</b>	Initiate a thread dump and save the data to a file with a time stamp
<b>zmvolume</b>	Manage storage volumes on your data-va virtual machine

## Using non-ASCII Characters in CLIs

If you use non-ASCII characters in the CLI, in order for the characters to display correctly, you must change this setting to the desired UTF-8 before running the CLI command. To change this, type

```
export LC_All=<UTF_locale>
```

## Provisioning (zmprov)

The **zmprov** tool performs all provisioning tasks in Horizon Files LDAP, including modifying account and COS attributes.

The syntax is `zmprov [cmd] [argument]`.

The syntax for modify can include the prefix “+” or “-” so that you can make changes to the attributes affected and do not need to reenter attributes that are not changing.

- Use + to add a new instance of the specified attribute name without changing any existing attributes.
- Use - to remove a particular instance of an attribute.

The following example would add the attribute **hzndataFileExRestricted** with the value “.zip” to user 1 and would not change the value of any other instances of that attribute.

```
zmprov ma user1 +hzndataFileExRestricted .zip
```

The attributes for tasks that can be used with `zmprov` are listed when you type `zmprov -h`.

Long Name	Short Name	Syntax, Example, and Notes
--help	-h	Displays usage
--file	-f	Use file as the input stream
--server	-s	{host}[:{port}] Server hostname and optional port



Long Name	Short Name	Syntax, Example, and Notes
--ldap	-l	Provision via LDAP instead of SOAP
--logpropertyfile	-L	Log 4j property file, valid only with -l
--verbose	-v	Verbose mode (dumps full exception stack trace)
--debug	-d/	Dbug mode (dumps SOAP messages)
--master	-m	Use the LDAP master. This is only valid with -l
--replace	-r	Allow replacement of safe-guarded multi-value attribute configured in localconfig key <b>zmprov_saveguarded_attrs</b>

The zmprov commands in the following table are divided into the tasks type.

Long Name	Short Name	Syntax, Example, and Notes
<b>Data Store Account Provisioning Commands</b>		
deleteAccount	da	Deletes guest accounts Syntax: {name@domain id adminName} zmprov da joe@domain.com
getAccount	ga	Finds guest accounts Syntax: {name@domain id adminName} zmprov ga joe@domain.com
getAllAccounts	gaa	Finds all guest accounts Syntax: [-v] [{domain}] zmprov -l gaa zmprov -l gaa -v domain.com
modifyAccount	ma	{name@domain id adminName} [attribute1 value1 etc] zmprov ma joe@domain.com hzndataAccountStatus maintenance
<b>COS Provisioning Commands</b>		
copyCos	cpc	{src-cos-name id} {dest-cos-name}
getCos	gc	{name id} zmprov gc Executive
getAllCos	gac	[-v] zmprov gac -v
modifyCos	mc	{name id} [attribute1 value1 etc]
renameCos	rc	{name id} {newName} zmprov rc Executive Business

Long Name	Short Name	Syntax, Example, and Notes
<b>Config Provisioning Commands</b>		
getAllConfig	gacf	[-v] All LDAP settings are displayed
getConfig	gcf	{name}
modifyConfig	mcf	attr1 value1 Modifies the Horizon Files LDAP settings
<b>Data Store General Commands</b>		
getMailboxInfo	<b>gmi</b>	{account}
getQuotaUsage	<b>gqu</b>	{server}
reIndexMailbox	<b>rim</b>	{name@domain id} {start status cancel} [{reindex-by} {value1} [value2...]]
RecalculateMailboxCounts	rnc	{name@domain id} When the quota usage is out of sync with the data in the user's data store, use this command to immediately recalculate the quota usage  <b>Important:</b> Recalculating quota usage should be schedule to run in off peak hours and run on one data store at a time
selectMailbox	<b>sm</b>	{account-name} [{zmmailbox commands}]
<b>Share Provisioning Commands</b>		
getShareInfo	<b>gsi</b>	{owner-name owner-id}
<b>Miscellaneous Provisioning Commands</b>		
describe	<b>desc</b>	[[ -v ] [ -ni ] [{entry-type}]]   [ -a {attribute-name} ] Prints all attribute names (account, domain, COS, servers, etc.)
flushCache	<b>fc</b>	zmprov flushCache [account cos] [name id]. Use this command to make changes available immediately
getAccountLogger	<b>gal</b>	[-s /--server hostname] {name@domain   id}

## Managing Guest Users' Class of Service

A default guest COS is assigned to guest accounts that are created when users outside of your organization accept an invitation to share Horizon files folders. A guest account is not provisioned in Horizon Workspace, but guest users can sign in and create a display name and set a password to view the shared items. The only folders they see in their Horizon Workspace are the folders that are shared with them.

This COS is not configurable from the Horizon Workspace administrator's Web client, but you can change defaults from the zmprov CLI.

To see the settings for the default guest COS, type

```
zmprov -l gc guest
```

Description of some of the guest default COS attributes that might need to be modified include:

- **Host Pool.** In an environment with multiple data-va nodes, this attribute controls the pool of data nodes from which the guest users' home server is picked:

- To add a data-va node to the host pool, type

```
zmprov mc guest +hzndataHostPool <server-ID>
```

- To remove a data-va node from the host pool, type

```
zmprov mc guest -hzndataHostPool <server-ID>
```

- To replace all data-va virtual machines in the host pool with a specific data-va, type

```
zmprov mc guest hzndataHostPool <server-ID>
```

- View which data-va nodes are in the host pool, type

```
zmprov gc guest hznHostPool
```

---

**Note:** *If the guest COS has not been modified to add specific data-va machines to the host pool, this command does not return a value. The default is that all data-va machines are enabled in the host pool.*

---

- **Guest Account's quota.** Quota does not need to be set for guest user accounts. Guest users work with files in folders that are shared with them by internal users. The internal user's quota is impacted when guest users add or delete files in the shared folder.

- **Types of files that guest users cannot upload to the Horizon files folder.** Each restricted extension must be prefixed with a dot (.). For example to exclude exe files, type as **.exe**.

```
zmprov mc guest hzndataFileExtensionRestricted { .type }
```

- **For Windows Preview to work in a guest account's Horizon folder, the guest COS must be modified.**

```
zmprov mc guest hzndataConverterHints UseMsPDFConverter
```

- **Password policies for guest accounts.** Guest users must set a password based on the password settings you set up. The default minimum length for a password is 6 characters and the maximum is 64 characters. You can change these settings and add more complex password rules.

- To change the length of a password

```
zmprov mc guest hzndataPasswordMinLength <#>
```

To require more complex passwords, set the following attributes.

- Minimum number of characters = hzndataPasswordMinNumericChars
- Minimum number of lower case characters = hzndataPasswordMinLowerCaseChars
- Minimum number of ASCII punctuation characters = hzndataPasswordMinPunctuationChars
- Minimum number of upper case characters = hzndataPasswordMinUpperCaseChars

## Changing SMTP Server Settings

SMTP authentication allows authorized mail clients from external networks to relay messages through the MTA. The SMTP server hostname and port number is configured when Horizon Workspace is installed.

To view the current SMTP server settings on the data-va, type

```
zmprov gcf get hzndataMtaHostname
```

To change a setting, type

```
zmprov mcf hzndataMtaHostname <value>
```

For example, to change the SMTP host name, type

```
zmprov mcf hzndataMtaHostname new.smtp.domain.com
```

Additional SMTP server attributes settings that might need to be changed.

- `zmprov mcf hzndataMtaAuthPassword <value>`
- `zmprov mcf hzndataMtaAuthAccount <value>`
- `zmprov mcf hzndataMtaAuthRequired <value>`
- `zmprov mcf hzndataMtaConnectionType <value>`
- `zmprov mcf hzndataMtaEnabled <value>`
- `zmprov mcf hzndataMtaPort <value>`

## Other Types of zmprov Commands

The following are general types of zmprov commands.

- To query if a value is set for a multi-valued attribute

```
zmprov gs server.com attribute=value
```

For example, to find out if the ldap service is enabled

```
zmprov gs example.com hzndataServiceEnabled=ldap
```

- To flush the cache to make changes to an account or COS available immediately

```
zmprov fc [account|cos|server] [name|id]
```

- Each account's Horizon files module has an index file associated with it. This index file is required to retrieve search results from the data store. To detect corrupted indexes, run **zmprov verifyIndex** as a sanity check against the specified data store index.

```
zmprov verifyIndex <user@example.com>
```

Diagnostic information is written to **stdout**. If problems are detected, a failure status is returned.

VerifyIndex locks the index while running, and checks every byte in the index. Therefore, it is not recommended to run this on a regular basis. The `zmprov verifyIndex` command should be used only when you need to make a diagnosis.

If VerifyIndex reports that the index is corrupted, you can repair the index by running **reIndexMailbox (rim)**.

```
zmprov rim <user@example.com> start
```

## Start/Stop/Restart Service on the Data-va (zmcontrol)

This command is run to start, to stop, or to restart the Horizon files services.

### Syntax

```
zmcontrol [ -v -h ] command [args]
```

## Description

Long Name	Short Name	Description
	-v	Displays ZCS software version
	-h	Displays the usage options for this command
	-H	Host name (localhost)
Command in...		
restart		Restarts all services and manager on this host
shutdown		Shutdown all services and manager on this host. When the manager is shutdown, you cannot query that status
start		Startup manager and all services on this host
startup		Startup manager and all services on this host
status		Display service status
stop		Stop all services but leaves the manager running

## Move Accounts from One Data-va to Another (zmmboxmove)

The CLI command **zmmboxmove** is used to move an account's data store from one data-va virtual machine to another. The destination data-va manages the overall move process. The move runs in the background and the account remains in maintenance mode until all of the data has been moved.

Data stores can be moved between data-va nodes. After the account's data store is moved to a new data-va, a copy still remains on the older data-va. You should check to see that all the data store content was moved successfully before purging the old data store.

## Syntax

```
zmmboxmove -a <email> --from <servername> --to <dest> [--sync]
```

## Description

Long Name	Short Name	Description
--account	-a	<arg> Email address of account to move
--help	-h	Displays the usage options for this command
--from	-f	<arg> Data-va hostname. Data-va where the --account data store is currently located
--to	-t	<arg> Destination data-va
--sync	-sync	Run synchronously

## Check Account Move Status (zmmboxmovequery)

The CLI command **zmmboxmovequery** is used to show ongoing accounts' data store moves on a data-va, both move-ins and move-outs.

### Syntax

```
zmmboxmovequery -a <account email> [-s <server to query>]
```

### Description

Long Name	Short Name	Description
--account	-a	<arg> Email address of account (all if omitted)
--help	-h	Displays the usage options for this command
--server	-s	<arg> Data-va hostname

## Purge the Old Account After a Move (zmpurgeoldmbox)

The CLI command **zmpurgeoldmbox** purges the data store from the older data-va after a data store move.

### Syntax

```
zmpurgeoldmbox -a <email@address> --from <servername> --to <servername>
```

### Description

Long Name	Short Name	Description
--account	-a	<arg> Email address of account to purge
--help	-h	Displays the usage options for this command
--server	-s	<arg> Data-va hostname

## Procedure to Move an Account

1. Go to the destination data-va and log in as the root user.
2. Change to the zimbra user, type  
su - zimbra
3. Move a Horizon account to a new data-va, type  
zmmboxmove -a useraccount --from <src> --to <dest> [sync]  
When the account move is complete, you receive a success or failure notification.
4. After the account move is complete, to refresh the information cached in memcached, reboot each Horizon Workspace Gateway VA and flush the cache.
  - a. On the gateway-va to restart memcached, as root type

```
/etc/rc.d/memcached restart
```

- b. Flush memcached without stopping
 

```
wget -O - --quiet http://<GatewayIP:6035>/flush
```
5. Before purging the old account, make sure that users can sign in and see all their files and folders.
6. Purge the account on the old data-va virtual machine. Type
 

```
zmpurgeoldmbox -a <email> -s <server_to_purge>
```

## Data-va Local Configuration Options (zmlocalconfig)

This command is used to set or get the local configuration for a data-va virtual machine. Use `zmlocalconfig -i` to see a list of supported properties that can be configured by an administrator.

### Syntax

```
zmlocalconfig [options]
```

To see the local config type `zmlocalconfig`

### Description

Long Name	Short Name	Description
<code>--config</code>	<code>-c</code>	<arg> File in which the configuration is stored
<code>--default</code>	<code>-d</code>	Show default values for keys listed in [args]
<code>--edit</code>	<code>-e</code>	Edit the configuration file, change keys and values specified. The [args] is in the key=value form
<code>--force</code>	<code>-f</code>	Allow editing of keys whose change is known to be potentially dangerous
<code>--help</code>	<code>-h</code>	Shows the help for the usage options for this tool
<code>--info</code>	<code>-i</code>	Shows documentation for keys listed in [args]
<code>--reload</code>	<code>-l</code>	Sends a SOAP request to the server to reload its local config
<code>--format</code>	<code>-m</code>	<arg> Shows the values in one of these formats: plain (default), xml, shell, export, nokey
<code>--changed</code>	<code>-n</code>	Shows the values for only those keys listed in the [args] that have been changed from their defaults
<code>--path</code>	<code>-p</code>	Shows which configuration file will be used
<code>--quiet</code>	<code>-q</code>	Suppress logging
<code>--random</code>	<code>-r</code>	This is used with the edit option. Sets the specified key to a random password string
<code>--show</code>	<code>-s</code>	Forces the display of password strings

Long Name	Short Name	Description
--unset	-u	Remove a configuration key. If this is a key with compiled-in defaults, set its value to the empty string
--expand	-x	Expand values

- If Microsoft Preview is enabled for Horizon files preview, you must set the URL on each data-va to point to the Microsoft Preview server.

```
zmlocalconfig -e ms_convert_url=(http://xx.xx.xx.xx|url)
```

## Data Store Account Management (zmailbox)

The **zmailbox** tool is used for data store account management. The command can help administrators debug issues with an account. It is useful in getting a list of folders, checking rights, searching the files, etc.

You can also invoke the **zmailbox** command from within the **zmprov** command. You enter **selectMailbox** within **zmprov** to access the **zmailbox** command connected to that specified account. You can then enter **zmailbox** commands until you type **exit**. Exit returns you to **zmprov**.

### Syntax

```
zmailbox [args] [cmd] [cmd-args ...]
```

### Description

Long Name	Short Name	Syntax, Example, and Notes
<b>Note:</b> The following three rows describe the authentication options. Only one option can be specified.		
--authTokenFile	-A	<arg> Authenticate with the auth token from file. This is the same as -a, but the auth token is read from the specified file.
--authToken	-a	<arg> Authenticate with auth token string from the command line. <ul style="list-style-type: none"> <li>• If no target account is specified, the target account is the authed account</li> <li>• If a target account is specified and this account is not the same account in the auth token, use delegated requests to access the target account</li> </ul> *See -m for specifying a target account
--zadmin	-z	Authenticate with the built-in admin name and password from localconfig. Use delegated requests to access the target account.
--help	-h	Display usage
--file	-f	<arg> Use file as input stream



<code>--url</code>	<code>-u</code>	<arg> http[s]://{host}[:{port}] of server to connect to
<code>--mailbox</code>	<code>-m</code>	{ name } Target account to open
<code>--timeout</code>	<code>-t</code>	<arg> Timeout (in seconds)
<code>--verbose</code>	<code>-v</code>	Verbose mode (dumps full exception stack trace)
<code>--debug</code>	<code>-d</code>	Debug mode (dumps SOAP messages)
<code>--protocol</code>	<code>-r</code>	<arg> Protocol to use for request/response [soap11, soap12, json]

Specific CLI tools are available for the different components of a data store. Usage is described in the CLI help for the following.

<code>zmailbox help commands</code>	help on all commands
<code>zmailbox help folder</code>	help on folder-related commands
<code>zmailbox help item</code>	help on item-related commands
<code>zmailbox help misc</code>	help on miscellaneous commands
<code>zmailbox help right</code>	help on right commands
<code>zmailbox help search</code>	help on search-related commands

## Examples

- To find the data store size for an account
 

```
zmailbox -z -m user@example.com gms
```
- To find rights granted on a folder
 

```
zmailbox -z -m user@example.com gfg /Briefcase/myfolder
```

## Metadata Dump (zmmetadump)

This command is a support tool that dumps the contents of an item's metadata in a human readable form.

### Syntax

```
zmmetadump -m <mailbox id/email> -i <item id> [--dumpster]
or zmmetadump -f <file containing encoded metadata>
```

## SOAP Format (zmssoap)

The zmssoap tool sends SOAP commands to the data-va.

### Syntax

```
zmssoap [options] <xpath1> [xpath2 xpath3...]
```

## Description

Long Name	Short Name	Description
<p><b>Note:</b> The following three rows describe the authentication options. Only one option can be specified.</p>		
--authTokenFile	-A	<arg> Authenticate with auth token from file
--authToken	-a	<p>&lt;arg&gt; Authenticate with auth token string from the command line.</p> <ul style="list-style-type: none"> <li>If no target account is specified, the target account is the authed account..</li> <li>If a target account is specified and this account is not the same account that is in the auth token, delegated requests to access the target account is used.</li> </ul> <p>*See <b>-m</b> for specifying a target account</p>
--zadmin	-z	<p>Authenticate with the built-in admin name and password from localconfig.</p> <p>Use delegated requests to access the target account.</p>
--help	-h	Prints usage information
--file	-f	<path> Read request from file
--jaxb		Force use of JAXB to aid building request from command line
--json		Use JSON instead of XML. (Switches on --jaxb options by default)
--mailbox	-m	{ name } Target account to open
--no-op	-n	Print the SOAP request only. Do not send it
--no-jaxb		Disallow use of JAXB to aid building request from the command line
--select		<xpath> Select an element or attribute from the response
--type	-t	<type> Displays the SOAP request type. Can either be mail, account, or admin
--url	-u	<p>SOAP service URL, usually http[s]://host:port/service/soap or https://host:port/service/admin/soap.</p> <p>Displays the server hostname and optional port value</p>
--use-session		Use a SOAP session.
--verbose	-v	Prints the SOAP request and other status information

Long Name	Short Name	Description
--very-verbose	-vv	Prints URLs and all requests and responses with envelopes

Element paths follow XPath syntax. The path of each subsequent element is relative to the previous one. To navigate up the element tree use “..” in the path. To specify attributes on the current element, use one or more @attr=val arguments. To specify element text, use “path/to/element=text”.

Example: zmssoap -z GetAccountInfoRequest/account=user1 @by=name

## Thread Dump (zmthrdump)

This command invokes a thread dump in the data-va virtual machine process and prints the output file. It also gives the option of saving the thread dump to a file and inserts a time stamp on the logfile.

### Syntax

```
zmthrdump [-h] [-i] [-t <timeout seconds>] [-p <pid file>] [-f <file>] [-o <out-file>]
```

### Description

Short Name	Description
-h	Displays help messages
-i	Appends the time stamp to the LOGFILE before invoking SIGQUIT
-p	Returns the PID to send SIGQUIT. The default value can be found in zmmailboxd_java.pid
-f	Specifies the LOGFILE to save the thread dump output in. The default value is zmmailbox.out
-o	Specifies the output file of the thread dump. The default value is stdout
-t	Specifies the timeout value (in seconds) to exit if the process becomes unresponsive. The default value is 30 seconds

## Manage Data Store Storage Volumes (zmvolume)

When the data-va virtual machine is set up, one current index volume and one current files volume are configured.

### Index Volumes

Each account is assigned to a permanent directory on the current index volume. As volumes become full, you can create a new current index volume for new accounts. Index volumes not marked “current” are still actively in use for the accounts assigned to them. Any index volume that is referenced by an account cannot be deleted.

## Files Volumes

When new files are added to an account, the files are saved in the current files volume. When the volume is full, you can configure a new current files volume. The current files volume receives all new files. A current volume cannot be deleted and file volumes that have files referencing the volume cannot be deleted.

This command can be used to manage storage volumes from the CLI.

### Syntax

```
zmvolume { -a|-d|-l|-e|-dc|-sc } <options>
```

### Description

Long Name	Short Name	Description
--add	-a	Adds a volume
--name	-n	<arg> Volume name
--type	-t	<arg> Volume type (primaryMessage, secondaryMessage, or index)
--path	-p	<arg> Root path
--compress	-c	<arg> Compress BLOBs; "true" or "false"
--compressionThreshold	-ct	<arg> Compression threshold; default is 4KB
--edit	-e	Edits a volume
--id	-id	<arg> Volume ID

Any of the options listed under -a can also be specified to have its value modified.

--delete	-d	Deletes a volume
--id	-id	<arg> Volume ID
--displayCurrent	-dc	Displays the current volumes
--help	-h	Shows the help for the usage options for this tool
--list	-l	Lists volumes
--id	-id	<arg> Volume ID. -id is optional
--server	-s	<arg> Data server hostname. Default is localhost
--setCurrent	-st	Sets the current volume
--id	-id	<arg> Volume ID
--turnOffSecondary	-ts	Turns off the current secondary message volume

#### ■ Add a volume

```
zmvolume -a -t primaryMessage -n <name> -p <path>
```

Type can be primaryMessage, secondaryMessage, or index

#### ■ List a volume

```
zmvolume -l
```

- Delete a volume  
    `zmvolume -d -id <id>`
- Edit a volume  
    `zmvolume -e -id <id>`



# Index

## A

- account index 12
- account management tool, data store 16
- account move, check status 14
- account move, purge old 14
- account provisioning, zmprov 9
- account, changing settings 11
- account, move to new server 13
- account, moving 14
- attribute list, how to find 6

## C

- CLI commands list 7
- CLI utilities 5, 7
- CLI, how to use 5
- config provisioning, zmprov 10
- COS provisioning, zmprov 9
- COS, default external 10

## D

- data store, zmprov 10
- data-va, start stop 12
- default external COS 10
- describe, attribute list 10

## F

- files volumes, data store 20
- flush cache 10, 12

## G

- guest account quota 11
- guest accounts, password policies 11
- guest accounts, using Windows Preview 11
- guest users, setting up 10

## I

- index volumes, data store 19

- index, for account 12

## L

- local configuration options 15
- local configuration, CLI 15
- localconfig list of properties 15

## M

- metadata 17
- Microsoft Preview, set URL on data-vas 16
- moving an account 14

## Q

- quota out of sync 10
- quota usage out of sync 10

## R

- recalculate account count command 10
- reindex 12

## S

- SMTP, change 11
- SOAP tool 17
- storage volume, manage 19
- syntax conventions 5
- syntax, modify 8

## T

- thread dump tool 19

## V

- verifyIndex 12
- virtual users, see guest users 10
- volume, add 20
- volume, delete 21
- volume, list 20
- volumes, managing with CLI 20

## Z

zmpov 8  
zmpov CLI 8