

# Setting Up Horizon 7 for Linux Desktops

VMware Horizon 7 Version 7.2

This document supports the version of each product listed and supports all subsequent versions until the document is replaced by a new edition. To check for more recent editions of this document, see <http://www.vmware.com/support/pubs>.

EN-002527-00

**vmware**<sup>®</sup>

You can find the most up-to-date technical documentation on the VMware Web site at:

<http://www.vmware.com/support/>

The VMware Web site also provides the latest product updates.

If you have comments about this documentation, submit your feedback to:

[docfeedback@vmware.com](mailto:docfeedback@vmware.com)

Copyright © 2016, 2017 VMware, Inc. All rights reserved. [Copyright and trademark information.](#)

**VMware, Inc.**  
3401 Hillview Ave.  
Palo Alto, CA 94304  
[www.vmware.com](http://www.vmware.com)

# Contents

Setting Up Horizon 7 for Linux Desktops	5
<b>1 Features and System Requirements</b>	<b>7</b>
Features of Horizon Linux Desktops	7
Overview of Configuration Steps for Horizon 7 for Linux Desktops	10
System Requirements for Horizon 7 for Linux	11
<b>2 Preparing a Linux Virtual Machine for Desktop Deployment</b>	<b>19</b>
Create a Virtual Machine and Install Linux	19
Prepare a Linux Machine for Remote Desktop Deployment	20
Install Dependency Packages for Horizon Agent	22
<b>3 Setting Up Active Directory Integration for Linux Desktops</b>	<b>25</b>
Integrating Linux with Active Directory	25
Setting Up Single Sign-on and Smart Card Redirection	26
<b>4 Setting Up Graphics for Linux Desktops</b>	<b>29</b>
Configure Supported RHEL Distributions for vGPU	29
Configure RHEL 6 for vDGA	34
Configure RHEL 7 for vSGA	37
<b>5 Installing Horizon Agent</b>	<b>41</b>
Install Horizon Agent on a Linux Virtual Machine	41
Configure the Certificate for Linux Agent	43
Upgrading the Horizon Agent on a Linux Virtual Machine	44
Uninstall Horizon 7 for Linux Machines	46
<b>6 Configuration Options for Linux Desktops</b>	<b>47</b>
Setting Options in Configuration Files on a Linux Desktop	47
Example Blast Settings for Linux Desktops	54
Examples of Client Drive Redirection Options for Linux Desktops	55
Suppress the vSphere Console Display of a Linux Desktop	55
<b>7 Create and Manage Linux Desktop Pools</b>	<b>57</b>
Create a Manual Desktop Pool for Linux	57
Manage Desktop Pool for Linux	58
Create an Automated Full-Clone Desktop Pool for Linux	59
Broker PowerCLI Commands	61

<b>8</b>	<b>Bulk Deployment of Horizon 7 for Manual Desktop Pools</b>	<b>65</b>
	Overview of Bulk Deployment of Linux Desktops	65
	Overview of Bulk Upgrade of Linux Desktops	67
	Create a Virtual Machine Template for Cloning Linux Desktop Machines	67
	Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops	69
	Sample Script to Clone Linux Virtual Machines	69
	Sample Script to Join Cloned Virtual Machines to AD Domain	73
	Sample Script to Join Cloned Virtual Machines to AD Domain Using SSH	76
	Sample Script to Upload Configuration Files to Linux Virtual Machines	79
	Sample Script to Upload Configuration Files to Linux Virtual Machines Using SSH	83
	Sample Script to Upgrade Horizon Agent on Linux Desktop Machines	87
	Sample Script to Upgrade Horizon Agent on Linux Virtual Machines Using SSH	91
	Sample Script to Perform Operations on Linux Virtual Machines	97
<b>9</b>	<b>Troubleshooting Linux Desktops</b>	<b>101</b>
	Collect Diagnostic Information for Horizon 7 for Linux Machine	101
	Troubleshooting Copy and Paste between Remote Desktop and Client Host	102
	Configuring the Linux Firewall to Allow Incoming TCP Connections	102
	View Agent Fails to Disconnect on an iPad Pro Horizon Client	102
	SLES 12 SP1 Desktop does not Auto Refresh after Drag and Drop	103
	SSO Fails to Connect to a PowerOff Agent	103
	Unreachable VM After Creating a Manual Desktop Pool for Linux	103
	<b>Index</b>	<b>105</b>

# Setting Up Horizon 7 for Linux Desktops

---

The *Setting Up Horizon 7 for Linux Desktops* document provides information about setting up a Linux virtual machine for use as a VMware Horizon<sup>®</sup> 7 desktop, including preparing the Linux guest operating system, installing Horizon Agent on the virtual machine, and configuring the machine in View Administrator for use in a Horizon 7 deployment.

## Intended Audience

This information is intended for anyone who wants to configure and use remote desktops that run on Linux guest operating systems. The information is written for experienced Linux system administrators who are familiar with virtual machine technology and datacenter operations.



# Features and System Requirements

---

With Horizon 6 or later, users can connect to remote desktops that run the Linux operating system.

This chapter includes the following topics:

- [“Features of Horizon Linux Desktops,”](#) on page 7
- [“Overview of Configuration Steps for Horizon 7 for Linux Desktops,”](#) on page 10
- [“System Requirements for Horizon 7 for Linux,”](#) on page 11

## Features of Horizon Linux Desktops

Horizon 7 version 7.2 introduces several new features for Linux desktops.

The following new features are supported for Horizon 7 version 7.2 release.

- Client Drive Redirection (CDR)
- USB Redirection support
- Audio output support for HTML Access
- Single sign-on support on RHEL 7 Workstation x64 and CentOS 7 x64
- Support for FIPS 140-2 mode on RHEL 6 x64 and RHEL 7 x64
- Support for K Desktop Environment (KDE) on CentOS 6 x64 and RHEL 6 x64
- Support for RHEL 6.9 x64 and CentOS 6.9 x64

The following list presents the key features for Horizon Linux Desktops.

### **Automated Full-Clone Desktop Pool**

Beginning with Horizon 7 version 7.0.2 release, you can create automated full-clone desktop pools for Linux desktops.

### **Manual Desktop Pool**

Machine source.

- **Managed Virtual Machine** - Machine source of the vCenter virtual machine. A managed virtual machine is supported for new and upgrade deployment.
- **Unmanaged Virtual Machine** - Machine source of other sources. An unmanaged virtual machine is only supported when the upgrade is from an unmanaged virtual machine deployment.

---

**NOTE** To ensure the best possible performance, do not use an unmanaged virtual machine.

---

**Multiple Monitors**

- vDGA/vGPU desktop supports a maximum resolution of 2560x1600 on four monitors.
- 2D/vSGA desktop on vSphere 6.0 or later supports a maximum resolution of 2048x1536 on four monitors or a maximum resolution of 2560x1600 on three monitors.

For Ubuntu 14.04/16.04, you must disable Compiz to support multiple monitors. See <http://kb.vmware.com/kb/2114809> for more information.

For SLES 12 SP1, you must use the default package with kernel level kernel-default-3.12.49-11.1. If you upgraded the package, the multi-monitor feature fails and the desktop is shown in one monitor.

**Lossless PNG**

Images and videos that are generated on a desktop are rendered on the client device in a pixel-exact manner.

**Software H.264 Encoder**

H.264 can improve the Blast Extreme performance for a Horizon desktop, especially under a low-bandwidth network. If the client side disabled H.264, Blast Extreme automatically falls back to JPEG/PNG encoding.

From Horizon 7 version 7.0.3 release, multiple monitors are supported.

**3D Graphics**

3D graphics is supported with the following combinations of Linux versions and graphics cards:

- vSGA is supported on RHEL 7 Workstation x64 with NVIDIA GRID K1 or K2 graphics cards.
- vDGA is supported on RHEL 6 Workstation x64 with NVIDIA GRID K1 or K2 graphics cards.
- vGPU is supported on RHEL 6 Workstation x64 with NVIDIA Maxwell M60 graphics cards.
- vGPU is supported on RHEL 7 Workstation x64 with NVIDIA Maxwell M60 graphics cards.
- vGPU is supported on RHEL 6 Workstation x64 with NVIDIA M6 graphics cards.
- vGPU is supported on RHEL 7 Workstation x64 with NVIDIA M6 graphics cards.

**Clipboard Redirection**

With the clipboard redirection feature, you can copy and paste a rich text or a plain text between a client host and a remote Linux desktop. You can set the copy/paste direction and the maximum text size using Horizon agent options. This feature is enabled by default. You can disable it during installation.

**Single Sign-on**

Single sign-on is supported on the following Linux versions:

- RHEL 6/7 Workstation x64
- CentOS 6/7 x64
- SLED 11 SP3/SP4 x64
- Ubuntu 14.04/16.04 x64

**Smart Card Redirection with SSO**

Smart card redirection is supported on RHEL 6 Workstation x64. Personal Identity Verification (PIV) cards and Common Access Cards (CAC) are supported. Mac client is not supported.



<b>Audio-in</b>	<p>Audio input redirection from a client host to a remote Linux desktop is supported. This feature is not based on the USB redirection function. If you want this feature enabled, you must select it during installation. You must select the system default audio in device "PulseAudio server (local)" in your application for the audio input. The feature is supported on:</p> <ul style="list-style-type: none"> <li>■ Ubuntu 14.04/16.04 x64</li> <li>■ CentOS 7 x64</li> <li>■ RHEL 7 Workstation x64</li> </ul>
<b>Audio-out</b>	<p>Audio output redirection is supported. This feature is enabled by default. To disable this feature, you must set the <code>RemoteDisplay.allowAudio</code> option to <code>false</code>. Beginning with Horizon 7 version 7.2 release, HTML Access provides audio-out support for Linux desktops.</p>
<b>Client Drive Redirection</b>	<p>The Client Drive Redirection (CDR) feature is available beginning with the Horizon 7 version 7.2 release. When you enable the CDR feature, your local system's shared folders and drives become available for you to access. You use the <code>tsc\client</code> folder that is located in your home directory in the remote Linux desktop. To use this feature, you must install the CDR components.</p>
<b>USB Redirection</b>	<p>The USB Redirection feature is available beginning with the Horizon 7 version 7.2 release. The feature gives you access to locally attached USB devices from remote Linux desktops. You must install the USB Redirection components and USB VHCI driver kernel module to use the USB feature. Ensure that you have been granted sufficient privileges to use the USB device that you want to redirect.</p> <hr/> <p><b>NOTE</b> USB 3.0 protocol is supported in Horizon 7 version 7.2 release.</p> <hr/>
<b>Keyboard Layout and Locale Synchronization</b>	<p>This feature specifies whether to synchronize a client's system locale and current keyboard layout with the Horizon Linux Agent desktops. When this setting is enabled or not configured, synchronization is allowed. When this setting is disabled, synchronization is not allowed.</p> <p>This feature is supported only for Horizon Client for Windows, and only for the English, French, German, Japanese, Korean, Spanish, Simplified Chinese and Traditional Chinese locales.</p>
<b>K Desktop Environment</b>	<p>Horizon 7 version 7.2 release, the K Desktop Environment (KDE) is supported on the following Linux distributions.</p> <ul style="list-style-type: none"> <li>■ CentOS 6 x64</li> <li>■ RHEL 6 x64</li> </ul>
<b>FIPS 140-2 Mode</b>	<p>The Federal Information Processing Standard (FIPS) 140-2 mode support is available beginning with Horizon 7 version 7.2 release. When FIPS 140-2 mode is enabled, Horizon Agent uses FIPS-compliant cryptographic algorithms for all communications. FIPS mode is supported on:</p> <ul style="list-style-type: none"> <li>■ RHEL 6 x64</li> <li>■ RHEL 7 x64</li> </ul> <hr/> <p><b>NOTE</b> The Transport Layer Security (TLS) protocol version 1.2 is required to support FIPS 140-2 mode.</p> <hr/>

Linux desktops and desktop pools have the following limitations:

- Virtual printing, location-based printing, and Real-Time Video are not supported.

---

**NOTE** When a security server is used, port 22443 must be open in the internal firewall to allow traffic between the security server and the Linux desktop.

---

## Overview of Configuration Steps for Horizon 7 for Linux Desktops

When you install and configure Horizon 7 for Linux desktops, you must follow a different sequence of steps depending on whether you install 2D graphics or 3D graphics on the virtual machines.

### 2D Graphics - Overview of Configuration Steps

For 2D graphics, take the following steps:

- 1 Review the system requirements for setting up a Horizon 7 for Linux deployment. See [“System Requirements for Horizon 7 for Linux,”](#) on page 11.
- 2 Create a virtual machine in vSphere and install the Linux operating system. See [“Create a Virtual Machine and Install Linux,”](#) on page 19.
- 3 Prepare the guest operating system for deployment as a desktop in a Horizon 7 environment. See [“Prepare a Linux Machine for Remote Desktop Deployment,”](#) on page 20.
- 4 Configure the Linux guest operating system to authenticate with Active Directory. This step is implemented with 3rd-party software, based on the requirements in your environment, and is not described in this guide.
- 5 Install Horizon Agent on the Linux virtual machine. See [“Install Horizon Agent on a Linux Virtual Machine,”](#) on page 41.
- 6 Create a desktop pool that contains the configured Linux virtual machines. See [“Create a Manual Desktop Pool for Linux,”](#) on page 57.

### 3D Graphics - Overview of Configuration Steps

You must complete the NVIDIA GRID vGPU, vDGA, or vSGA configuration on the Linux virtual machines before you install Horizon Agent on the machines and deploy a desktop pool in View Administrator.

- 1 Review the system requirements for setting up a Horizon 7 for Linux deployment. See [“System Requirements for Horizon 7 for Linux,”](#) on page 11.
- 2 Create a virtual machine in vSphere and install the Linux operating system. See [“Create a Virtual Machine and Install Linux,”](#) on page 19.
- 3 Prepare the guest operating system for deployment as a desktop in a Horizon 7 environment. See [“Prepare a Linux Machine for Remote Desktop Deployment,”](#) on page 20.
- 4 Configure the Linux guest operating system to authenticate with Active Directory. This step is implemented with 3rd-party software, based on the requirements in your environment, and is not described in this guide.
- 5 Configure 3D capabilities on your ESXi hosts and the Linux virtual machine. Follow the procedures for the 3D feature you intend to install.
  - See [“Configure Supported RHEL Distributions for vGPU,”](#) on page 29.
  - See [“Configure RHEL 6 for vDGA,”](#) on page 34.
  - See [“Configure RHEL 7 for vSGA,”](#) on page 37.
- 6 Install Horizon Agent on the Linux virtual machine. See [“Install Horizon Agent on a Linux Virtual Machine,”](#) on page 41.

- 7 Create a desktop pool that contains the configured Linux virtual machines. See “[Create a Manual Desktop Pool for Linux](#),” on page 57.

## Bulk Deployment

With View Administrator, you can only deploy Linux virtual machines in a manual desktop pool. With vSphere PowerCLI, you can develop scripts that automate the deployment of a pool of Linux desktop machines. See [Chapter 8, “Bulk Deployment of Horizon 7 for Manual Desktop Pools,”](#) on page 65.

## System Requirements for Horizon 7 for Linux

To install Horizon 7 for Linux, your Linux system must meet certain requirements for the operating system, Horizon 7, and vSphere platform.

### Supported Linux Versions for Horizon Agent

The following table lists the Linux operating systems that are supported on virtual machines in a desktop pool.

**Table 1-1.** Supported Linux Operating Systems for View Agent

Linux Distribution	Architecture
Ubuntu 14.04 and 16.04	x64
<b>NOTE</b> Disable Compiz to avoid poor performance. See <a href="http://kb.vmware.com/kb/2114809">http://kb.vmware.com/kb/2114809</a> for more information.	
Ubuntu 12.04	x64
RHEL 6.6, 6.7, 6.8, 6.9, 7.2 and 7.3	x64
CentOS 6.6, 6.7, 6.8, 6.9, 7.2, and 7.3	x64
NeoKylin 6 Update 1	x64
SLED 11 SP3/SP4, SLED 12 SP1/SP2	x64
SLES 12 SP1/SP2	x64

**NOTE** Linux agent has dependency packages on some Linux distribution. See “[Install Dependency Packages for Horizon Agent](#),” on page 22 for more information.

### Required Platform and Horizon 7 Software Versions

To install and use Horizon 7 for Linux, your deployment must meet certain requirements for the vSphere platform, Horizon 7, and the Horizon Client software.

**Table 1-2.** Required Platform and Horizon 7 Software Versions

Platform and Software	Supported Versions
vSphere platform version	<ul style="list-style-type: none"> <li>■ vSphere 6.0 U2 or a later release</li> <li>■ vSphere 6.5 or a later release</li> </ul>
Horizon environment	<ul style="list-style-type: none"> <li>■ Horizon Connection Server 7.2</li> </ul>
Horizon Client software	<ul style="list-style-type: none"> <li>■ Horizon Client 4.5.0 for Android</li> <li>■ Horizon Client 4.5.0 for Windows</li> <li>■ Horizon Client 4.5.0 for Linux</li> <li>■ Horizon Client 4.5.0 for Mac OS X</li> <li>■ Horizon Client 4.5.0 for iOS (iPad Pro)</li> <li>■ HTML Access 4.5.0 on Chrome</li> <li>■ Zero clients are not supported</li> </ul>

## TCP Ports Used By Linux Virtual Machines

View Agent and Horizon Clients use TCP ports for network access between each other and various View server components.

**Table 1-3.** TCP Ports Used By Linux Virtual Machines

Source	Port	Target	Port	Protocol	Description
Horizon Client	*	Linux Agent	22443	TCP	Blast if Blast Security Gateway is not used
Security Server, View Connection Server, or Access Point appliance	*	Linux Agent	22443	TCP	Blast if Blast Security Gateway is used
View Agent	*	View Connection Server	4001, 4002	TCP	JMS SSL traffic.

**NOTE** For more information on TCP and UDP ports used by clients, see TCP and UDP Ports Used by Clients and View Agent in the *Horizon Client and View Agent Security* in View document.

## Verify the Linux Account Used By Linux Virtual Machines

The following table lists the account name and account type used by Linux virtual machines.

**Table 1-4.** Account Name and Account Type

Account Name	Account Type	Used By
root	Linux OS built-in	Java Standalone Agent, mksvchanserver, shell scripts
vmwblast	created by Linux Agent installer	VMwareBlastServer
<current login user>	Linux OS built-in or AD user or LDAP user	python script

## Desktop Environment

Horizon 7 for Linux Desktop supports multiple desktop environments on different Linux distributions. The following table lists the default desktop environments for each Linux distribution supported by Horizon 7 for Linux Desktop.

**Table 1-5.** Supported Desktop Environments

Linux Distribution	Default Desktop Environment	Desktop Environment Supported by Horizon 7 for Linux Desktop
Ubuntu 14.04/16.04	Unity	Gnome Fallback/Flashback (Metacity)
Ubuntu 12.04	Unity	Unity
RHEL/CentOS 6	Gnome	Gnome, K Desktop Environment (KDE)
RHEL/CentOS 7	Gnome	Gnome
SLED 11 SP4	Gnome	Gnome
SLED 12 SP1/SP2	Gnome	Gnome
SLES 12 SP1/SP2	Gnome	Gnome
NeoKylin 6 Update 1	Mate	Mate

To install the Gnome Fallback/Flashback (Metacity) desktop environment on Ubuntu 14.04/16.04, see the VMware KB article <http://kb.vmware.com/kb/2114809> for more information.

Use the following information to install KDE as the default desktop environment on RHEL/CentOS 6 distributions.

---

**NOTE** Single sign-on (SSO) for KDE only works if you install it using the steps described below.

---

- 1 Install the RHEL/CentOS 6 OS with the default desktop environment setting and Gnome will be installed.
- 2 Install KDE using the following command.

```
sudo yum groupinstall "X Window System" "KDE Desktop"
```

If you enabled SSO on a Linux distribution that has multiple desktop environments installed, use the following information to select the desktop environment..

- For Ubuntu 14.04/16.04, enable the UseGnomeFlashback option in the `/etc/vmware/viewagent-custom.conf` file to force the end user to use Gnome Fallback/Flashback (Metacity).
- For RHEL/CentOS 6, the end users must specify the desktop environment name `kde` or `gnome` in the `~/.dmrc` file to determine what will be used in their next SSO login session. For example, to use KDE as the default desktop environment, the end user must include the following setting in their `~/.dmrc` file.

```
[Desktop]
Session=kde
```

After the initial setup, the end user must log out or reboot the Linux system to make KDE, for the above example, as the default desktop in their next login session.

If you disabled SSO on the Linux distribution that have multiple desktop environments installed, the end user has to select the desired desktop environment when they log in to that Linux distribution.

## VHCI Driver for USB Redirection

The USB redirection feature is supported beginning with Horizon 7 version 7.1 for Linux desktops. The feature has a dependency on the USB Virtual Host Controller Interface (VHCI) kernel driver. You must patch the VHCI driver to support USB 3.0.

The Horizon for Linux installer includes the VHCI driver binary for the default kernel of the supported Linux distributions. It installs the VHCI driver when the USB redirection feature is selected. The following table lists the default kernel versions that the Horizon for Linux Desktop installer will install.

**Table 1-6.** Default Kernel Versions

Linux Distribution	Default Kernel Version
RHEL/CentOS 6.9	2.6.32-696.el6.x86_64
SUSE 12 SP2	4.4.21-69-default
RHEL/CentOS 7.3	3.10.0-514.el7.x86_64
Ubuntu 14.04	3.13.0-24-generic
Ubuntu 16.04	4.4.0-21-generic

If your Linux system uses a kernel version that is different from the default versions included with the Horizon for Linux installer, you must download the USB VHCI source code from <https://sourceforge.net/projects/usb-vhci/files/linux%20kernel%20module/>. You must then compile the VHCI driver source code and install the resulting binary on your Linux system.

---

**NOTE** The VHCI driver installation must be done before the installation of Horizon for Linux.

---

After you download the latest version of the USB VHCI driver source code, use the following commands to compile and install it on your Linux system. For example, if you unpack the installation file, `VMware-horizonagent-linux-x86_64-<version>-<build-number>.tar.gz`, under the `/install_tmp/` directory, the *full-path-to-patch-file* is `/install_tmp/VMware-horizonagent-linux-x86_64-<version>-<buildnumber>/resources/vhci/patch/vhci.patch` and the patch command to use is

```
# patch -p1 < /install_tmp/VMware-horizonagent-linux-x86_64-<version>-<build-  
number>/resources/vhci/patch/vhci.patch
```

**Table 1-7.** Compile and Install USB VHCI Driver

Linux Distribution	Steps to Compile and Install USB VHCI Driver
Ubuntu 14.04	Compile and install the VHCI drivers.
Ubuntu 16.04	<pre># tar -xzvf vhci-hcd-1.15.tar.gz # cd vhci-hcd-1.15 # patch -p1 &lt; full-path_to_patch-file # make clean &amp;&amp; make &amp;&amp; make install</pre>
RHEL/CentOS 6.9	1 Install the dependency packages.
RHEL/CentOS 7.3	<pre># yum install gcc-c++ # yum install kernel-devel-\$(uname -r) # yum install kernel-headers-\$(uname -r) # yum install patch</pre>
	2 Compile and install the VHCI drivers.
	<pre># tar -xzvf vhci-hcd-1.15.tar.gz # cd vhci-hcd-1.15 # patch -p1 &lt; full-path_to_patch-file # make clean &amp;&amp; make &amp;&amp; make install</pre>
SUSE 11 SP4	1 Find out the version of the current kernel package
SUSE 12 SP2	<pre># rpm -qa   grep kernel-default-\$(echo \$(uname -r)   cut -d '-' -f 1,2)</pre> <p>The output is the name of the kernel package currently installed. If, for example, the package name is <code>kernel-default-3.0.101-63.1</code>, then the current kernel package version is <code>3.0.101-63.1</code>.</p>
	2 Install the dependency packages.
	a For SUSE 11, install the <code>kernel-source</code> and <code>kernel-default-devel</code> packages that match the current kernel; the <code>gcc</code> and the <code>patch</code> packages.
	<pre>#zypper install --oldpackage kernel-source-&lt;kernel-package-version&gt; \ kernel-default-devel-&lt;kernel-package-version&gt; gcc patch</pre> <p>For example:</p> <pre>#zypper install --oldpackage kernel-source-3.0.101-63.1 kernel-default- devel-3.0.101-63.1 gcc patch</pre>
	b For SUSE 12, install the <code>kernel-devel</code> , <code>kernel-default-devel</code> , <code>kernel-macros</code> , and the <code>patch</code> packages.
	<pre>#zypper install --oldpackage kernel-devel-&lt;kernel-package-version&gt; \ kernel-default-devel-&lt;kernel-package-version&gt; kernel-macros-&lt;kernel-package- version&gt; patch</pre> <p>For example:</p> <pre>#zypper install --oldpackage kernel-devel-4.4.21-90.1 kernel-default- devel-4.4.21-90.1 kernel-macros-4.4.21-90.1 patch</pre>
	3 Compile and install the VHCI drivers.
	<pre># tar -xzvf vhci-hcd-1.15.tar.gz # cd vhci-hcd-1.15 # patch -p1 &lt; full-path_to_patch-file # mkdir -p linux/\$(echo \$(uname -r)   cut -d '-' -f 1)/drivers/usb/core # cp /lib/modules/\$(uname -r)/source/include/linux/usb/hcd.h linux/\$(echo \$ (uname -r)   cut -d '-' -f 1)/drivers/usb/core # make clean &amp;&amp; make &amp;&amp; make install</pre>

If your Linux kernel version is changed, you must recompile and reinstall the VHCI driver, but you do not need to reinstall Horizon for Linux.

## Virtual Machine Settings for 2D and vSGA Graphics

When you create certain Horizon 7 for Linux virtual machines, you must change the memory settings and configuration parameters to the minimum values recommended.

Virtual machines that are configured to use NVIDIA vDGA use the NVIDIA physical graphic card. Virtual machines that are configured to use NVIDIA GRID vGPU use the NVIDIA virtual graphic card, which is based on the NVIDIA physical graphic accelerator. You do not need to change the Video Memory (vRAM) settings and configuration parameters for these virtual machines.

Virtual machines that are configured to use 2D or vSGA graphics use the VMware virtual graphic card and you must change the following settings for these types of virtual machines:

- Video Memory (vRAM) settings
- Configuration parameters
- 3D Memory settings
- vCPU and virtual memory settings for performance requirement

### Video Memory (vRAM) Settings

When you create a Linux virtual machine in vSphere Client, configure the vRAM size as shown in [Table 1-8](#). Set the vRAM size that is recommended for the number and resolution of the monitors that you configure for the virtual machine.

**Table 1-8.** Recommended vRAM Settings for 2D or vSGA Graphics

vRAM Size	Number of Monitors	Maximum Resolution
10 MB	1	1600x1200 or 1680x1050
12 MB	1	1920x1440
32 MB	1	2560x1600
48 MB	2	2048x1536
80 MB	2	2560x1600
128 MB	3	2560x1600
128 MB	4	2048x1536

These vRAM sizes are the minimum recommendations. If more resources are available on the virtual machine, set the vRAM to larger values for improved video performance.

10 MB is the minimum vRAM size recommendation for a machine that is configured with a single monitor at the lowest resolution.

You must power off the virtual machine to set the number of displays and the amount of video memory to use, as described in [“Create a Virtual Machine and Install Linux,”](#) on page 19.

Horizon Connection Server 7 does not automatically configure the vRAM settings on Linux virtual machines like it does on Windows virtual machines. You must manually configure the vRAM settings in vSphere Client.

If a Linux virtual machine is configured with a smaller vRAM size than is recommended, the following issues might occur:

- Desktop sessions might be disconnected right after the initial connection is made.
- Autofit might fail to work. The desktop is then displayed in a small area of the screen.



If a Linux virtual machine's **Number of displays** value is less than the actual required count, one or more monitors display blank for the desktop.

If you encounter an autofit issue with the recommended settings, you can specify a larger vRAM size. vSphere Client permits a maximum vRAM size of 128 MB. If your specified size exceeds 128 MB, you must modify the vmx configuration file manually. The following example specifies a vRAM size of 256 MB:

```
svga.vramSize = "268435456"
```

## Configuration Parameters

To display the Linux remote desktop on multiple monitors, you must set certain configuration parameters for the virtual machine. The general steps to set a configuration parameter for a virtual machine are as follows:

- 1 Power off the virtual machine.
- 2 In the vSphere Web Client, right-click the virtual machine and select **Edit Settings**.
- 3 Click the **VM Options** tab and click **Advanced**.
- 4 Click **Edit Configuration** and then **Add Row**.
- 5 Enter the configuration parameter name and value.
- 6 Click **OK** to save the changes.

You must set the following configuration parameters:

- Set `svga.autodetect` to false.
 

```
svga.autodetect="false"
```
- Calculate the `svga.maxWidth` and `svga.maxHeight` values according to the number and orientation (horizontal or vertical) of the display monitors. The general rule is that the `svga.maxWidth` and `svga.maxHeight` values must be large enough to support all the displays. For example, to support four displays at the maximum resolution of 2560x1600, you must set the following values:

```
svga.maxHeight="3200"
svga.maxWidth="10240"
```

If you have multiple monitors, you must set these configuration parameters. Otherwise, you might encounter one or more of the following problems:

- The desktop is displayed on some of the monitors and the other monitors are blank.
- A keystroke is displayed multiple times.
- The desktop becomes slow.
- The desktop is displayed in a small area of the screen.

## Screen Size Limitation of 4096x4096 Monitors

For RHEL 6.8/6.9/7.3, CentOS 6.8/6.9/7.3, Ubuntu 16.04, SLED 12 SP2, and SLES 12 SP2, the maximum screen size for 2D and vSGA is 4096x4096. When you run the `xrandr` command, the first line of the output has maximum 4096x4096.

For Ubuntu 14.04, the limitation is also introduced if you install the latest patches from the official Ubuntu repositories.

Multiple-monitor connection might require a screen size larger than 4096x4096. To bypass this limitation, use one of the following solutions:

- If you have to use VMware Hardware version 11 (HWv11) or later for your virtual machine, add the following line into the virtual machine's VMX configuration file:

```
mks.enable3d = TRUE
```

With this solution, the Linux operating system can report 3D capabilities to software applications, such as Chrome. However, doing so might impact the Linux system's performance.

- If your virtual machine can use VMware Hardware version 10, use the following line in your virtual machine's VMX file:

```
virtualHW.version = "10"
```

This solution is not applicable for RHEL 6.8 and CentOS 6.8.

To make this solution work on Ubuntu 16.04 systems, you must install the latest patches from the official Ubuntu repositories.

### **vCPU and Memory Settings**

To improve the performance of a 2D or vSGA desktop, set more vCPUs and virtual memory for the Linux virtual machine. For example, set 2 vCPUs and 2 GB of virtual memory.

For the large screen of multiple monitors, such as four monitors, set 4 vCPUs and 4 GB of virtual memory for the virtual machine.

For the video playback purpose in a 2D or vSGA desktop, set 4 vCPUs and 4 GB of virtual memory for the virtual machine.

### **3D Memory Settings**

To improve performance in a vSGA multiple monitor environment, set the **3D Memory** setting for the virtual machine to 1 GB or larger.

# Preparing a Linux Virtual Machine for Desktop Deployment

---

# 2

Setting up a Linux desktop involves creating a Linux virtual machine and preparing the operating system for remote desktop deployment.

This chapter includes the following topics:

- [“Create a Virtual Machine and Install Linux,”](#) on page 19
- [“Prepare a Linux Machine for Remote Desktop Deployment,”](#) on page 20
- [“Install Dependency Packages for Horizon Agent,”](#) on page 22

## Create a Virtual Machine and Install Linux

You create a new virtual machine in vCenter Server for each remote desktop that is deployed in Horizon 7. You must install your Linux distribution on the virtual machine.

### Prerequisites

- Verify that your deployment meets the requirements for supporting Linux desktops. See [“System Requirements for Horizon 7 for Linux,”](#) on page 11.
- Familiarize yourself with the steps for creating virtual machines in vCenter Server and installing guest operating systems. See “Creating and Preparing Virtual Machines” in the *Setting Up Virtual Desktops in Horizon 7* document.
- Familiarize yourself with the recommended video memory (vRAM) values for the monitors you will use with the virtual machine. See [“System Requirements for Horizon 7 for Linux,”](#) on page 11.

### Procedure

- 1 In vSphere Web Client or vSphere Client, create a new virtual machine.

- 2 Configure custom configuration options.
  - a Right-click the virtual machine and click **Edit Settings**.
  - b Specify the number of vCPUs and the vMemory size.  
 For recommended values, follow the guidelines in the installation guide for your Linux distribution.  
 For example, Ubuntu 12.04 recommends configuring 2048 MB for vMemory and 2 vCPUs.
  - c Select **Video card** and specify the number of displays and the total video memory (vRAM).  
 Set the vRAM size in vSphere Web Client for virtual machines that use 2D or vSGA, which use the VMware driver. The vRAM size has no affect on vDGA or NVIDIA GRID vGPU machines, which use NVIDIA drivers.  
 For recommended values, follow the guidelines in *System Requirements for Horizon 7 for Linux*. Do not use the Video Memory Calculator.
- 3 Power on the virtual machine and install the Linux distribution.
- 4 Configure the desktop environment to use for the specific Linux distribution.  
 See the Desktop Environment section in [“System Requirements for Horizon 7 for Linux,”](#) on page 11 for additional information.
- 5 Ensure that the system hostname is resolvable to 127.0.0.1.

## Prepare a Linux Machine for Remote Desktop Deployment

You must perform certain tasks to prepare a Linux machine for use as a desktop in a Horizon 7 deployment.

Before a Linux machine can be managed by Horizon 7, the machine must be able to communicate with Connection Server. You must configure networking on the Linux machine so that the Linux machine can ping the Connection Server instance using its FQDN (fully qualified domain name).

Open VMware Tools (OVT) are pre-installed on RHEL 7, CentOS 7, SLED 12, and SLES 12 machines. If you are preparing either of these machines for use as a remote desktop, you can skip steps 1 through 5 in the following procedure, which describe how to install VMware Tools by manually running the installer.

If you are using an Ubuntu 16.04 machine, install OVT on it. If you are preparing this machine for use as a remote desktop, you can skip steps 1 through 5 in the following procedure and manually install OVT on your Ubuntu 16.04 machine using the following command:

```
apt-get install open-vm-tools-desktop
```

### Prerequisites

- Verify that a new virtual machine (VM) was created in vCenter Server and your Linux distribution was installed on the machine
- Familiarize yourself with the steps for mounting and installing VMware Tools on a Linux VM. See "Manually Install or Upgrade VMware Tools in a Linux Virtual Machine" in the *vSphere Virtual Machine Administration* document.
- Familiarize yourself with the steps for configuring your Linux machine to be resolvable through DNS. These steps vary for the different Linux distributions and releases. For instructions, consult the documentation for your Linux distribution and release.

### Procedure

- 1 In vSphere Web Client or vSphere Client, mount the VMware Tools virtual disk on the VM.

- 2 Right-click the VMware Tools installer file, `VMwareTools.x.x.x-xxxx.tar.gz`, click **Extract to**, and select the desktop for your Linux distribution.

The `vmware-tools-distrib` folder is extracted to the desktop.

- 3 On the VM, log in as root and open a terminal window.
- 4 Uncompress the VMware Tools tar installer file.

For example:

```
tar xzpf /mnt/cdrom/VMwareTools-x.x.x-yyyy.tar.gz
```

- 5 Run the installer and configure VMware Tools.

The command might vary slightly in different Linux distributions. For example:

```
cd vmware-tools-distrib
sudo ./vmware-install.pl -d
```

Usually, the `vmware-config-tools.pl` configuration file runs after the installer file finishes running.

- 6 Map the Linux machine's host name to 127.0.0.1 in the `/etc/hosts` file.

For RHEL, CentOS, SLES, and SLED, you must manually map the host name to 127.0.0.1 because it is not automatically mapped. For Ubuntu, this step is not necessary because the mapping is there by default. This step is also not necessary when you bulk deploy desktops because the cloning process adds this mapping.

---

**NOTE** If you change the Linux machine's host name after installing Horizon Agent, you must map the new host name to 127.0.0.1 in the `/etc/hosts` file. Otherwise, the old host name will continue to be used.

---

- 7 For RHEL 7 and CentOS 7, verify that `virbr0` is disabled.

```
virsh net-destroy default
virsh net-undefine default
service libvirtd restart
```

- 8 Ensure that the View Connection Server instances in the pod can be resolved through DNS.
- 9 Configure the Linux machine so that the default runlevel is 5.

The runlevel must be 5 for the Linux desktop to work.

- 10 On an Ubuntu machine that was configured to authenticate with an OpenLDAP server, set the fully qualified domain name on the machine.

This step ensures that the information can be displayed correctly in the User field on the Sessions page in View Administrator. Edit the `/etc/hosts` file as follows:

- a `# nano /etc/hosts`
- b Add the fully qualified domain name. For example: `127.0.0.1 hostname.domainname hostname.`
- c Exit and save the file.

- 11 For SUSE, disable Change Hostname via DHCP. Set the hostname or domain name.

- a In Yast, click **Network Settings**.
- b Click the **Hostname/DNS** tab.
- c Deselect **Change Hostname via DHCP**.
- d Enter the hostname and the domain name.
- e Click **OK**.

After installing VMware Tools, if you upgrade the Linux kernel, VMware Tools might stop running. To resolve the problem, see <http://kb.vmware.com/kb/2050592>.

## Install Dependency Packages for Horizon Agent

Horizon Agent for Linux has some dependency packages unique to a Linux distribution. You must install these packages before installing Horizon Agent for Linux.

### Prerequisites

Verify that a new virtual machine (VM) is created in vCenter Server and your Linux distribution is installed on the machine.

### Procedure

- 1 Install the mandatory packages that are not installed or upgraded by default. The installer breaks the installation if any package does not meet the requirement.

**Table 2-1.** Mandatory Dependency Packages

Linux Distribution	Packages
SLES 11 SP3/SP4 Upgrade xorg-x11-server to a version later than 7.4.27.111.1	<code>zypper install xorg-x11-server</code>
SLES 12 SP1/SLES 12 SP1 Upgrade xf86-video-vmware to a version later than 13.0.2-3.2 from the SUSE repository	<ol style="list-style-type: none"> <li>1 Register SUSE 12 to enable the SUSE repositories. <code>SUSEConnect -r <i>Registration Code</i> -e <i>Email</i></code></li> <li>2 Update the xf86-video-vmware version. <code>zypper install xf86-video-vmware</code></li> </ol>
SLES 12	<p>Install python-gobject2 is required for SLES 12 Linux desktop when you are installing Horizon Agent.</p> <ol style="list-style-type: none"> <li>1 Register SUSE 12 to enable the SUSE repositories. <code>SUSEConnect -r <i>Registration Code</i> -e <i>Email</i></code></li> <li>2 Install python-gobject2. <code>zypper install python-gobject2</code></li> </ol>
Ubuntu 14.04 Upgrade indicator-session to 12.10.5+15.04.20150327, available in <a href="https://launchpad.net/ubuntu/wily/amd64/indicator-session/12.10.5+15.04.20150327-0ubuntu1">https://launchpad.net/ubuntu/wily/amd64/indicator-session/12.10.5+15.04.20150327-0ubuntu1</a>	<code>wget http://launchpadlibrarian.net/201393830/indicator-session_12.10.5+15.04.20150327-0ubuntu1_amd64.deb</code> <code>sudo dpkg -i ./indicator-session_12.10.5+15.04.20150327-0ubuntu1_amd64.deb</code>
Ubuntu 16.04	<code>apt-get install python-dbus python-gobject</code>

- 2 Install the optional package for Horizon Agent.
  - By default, RHEL or CentOS 6.7 has glibc-2.12-1.166.el6.x86\_64 installed which might cause a deadlock issue. As a result, the desktop connection is stuck. To overcome this issue, you must upgrade glibc to the latest version from an online repository.

```
sudo yum install glibc
```

- On Ubuntu 14.04 desktops with multiple monitors, gnome-session-fallback is needed to disable Compiz for better performance..

```
sudo apt-get install gnome-session-fallback
```

- On Ubuntu 16.04 desktops with multi-monitors, `gnome-session-flashback` is needed to disable Compiz for better performance..

```
sudo apt-get install gnome-session-flashback
```





# Setting Up Active Directory Integration for Linux Desktops

# 3

View uses the existing Microsoft Active Directory (AD) infrastructure for user authentication and management. You can integrate the Linux desktops with Active Directory so that users can log in to a Linux desktop using their Active Directory user account.

This chapter includes the following topics:

- [“Integrating Linux with Active Directory,”](#) on page 25
- [“Setting Up Single Sign-on and Smart Card Redirection,”](#) on page 26

## Integrating Linux with Active Directory

Multiple solutions exist to integrate Linux with Active Directory (AD) and Horizon 7 for Linux Desktop has no dependency on which solution is used.

The following solutions are known to work in a Horizon 7 for Linux Desktop environment:

- OpenLDAP Server Pass-through Authentication
- System Security Services Daemon (SSSD) LDAP Authentication against the Microsoft Active Directory
- Winbind Domain Join

At a high level, the OpenLDAP Pass-through authentication solution involves the following steps:

- 1 Install Certificate Services on the Active Directory to enable LDAPS (Lightweight Directory Access Protocol over SSL).
- 2 Setup an OpenLDAP server.
- 3 Synchronize user information (except password) from the Active Directory to the OpenLDAP server.
- 4 Configure the OpenLDAP server to delegate password verification to a separate process such as `ssslauthd`, which can perform password verification against the Active Directory.
- 5 Configure the Linux desktops to use a LDAP client to authenticate users with the OpenLDAP server.

The SSSD LDAP authentication against the Microsoft Active Directory solution involves the following steps:

- 1 Install the Certificate Services on the Active Directory to enable LDAPS.
- 2 Configure the SSSD in the Linux desktop to directly use LDAP authentication against the Microsoft Active Directory.

The Winbind Domain Join solution involves the following steps:

- 1 Install the Winbind, Samba, and Kerberos packages on the Linux desktop.
- 2 Join the Linux desktop to the Microsoft Active Directory.

If you use the LDAP-based solutions, you need to do the configuration in a template virtual machine and no additional steps are required in the cloned virtual machines.

If you use the Winbind Domain Join solution or other Kerberos authentication-based solution, you need join the template virtual machine to the Active Directory, and re-join the cloned virtual machine to the Active Directory. For example, use the following command:

```
sudo /usr/bin/net ads join -U <domain
user>%<domain password>
```

Use the following options to run the domain re-join command on a cloned virtual machine for the Winbind solution:

- Remote connect such as SSH or vSphere PowerCLI to each virtual machine and run the command. For more information on scripts, see [Chapter 8, “Bulk Deployment of Horizon 7 for Manual Desktop Pools,”](#) on page 65.
- Include the command to a shell script and specify the script path to Horizon agent option `RunOnceScript` in the `/etc/vmware/viewagent-custom.conf` file. For more information, see [“Setting Options in Configuration Files on a Linux Desktop,”](#) on page 47.

---

**NOTE** For ease of deployment, use the SSSD LDAP authentication against the Microsoft Active Directory solution.

---

## Setting Up Single Sign-on and Smart Card Redirection

To set up single sign-on (SSO) and smart card redirection, you must perform some configuration steps.

### Single Sign-on

The Horizon View single sign-on module talks to PAM (pluggable authentication modules) in Linux and does not depend on the method that you use to integrate Linux with Active Directory (AD). Horizon View SSO is known to work with the OpenLDAP and Winbind solutions that integrate Linux with AD.

By default, SSO assumes that AD's `sAMAccountName` attribute is the login ID. To ensure that the correct login ID is used for SSO, you must perform the following configuration steps if you use the OpenLDAP or Winbind solution:

- For OpenLDAP, set `sAMAccountName` to `uid`.
- For Winbind, add the following statement to the configuration file `/etc/samba/smb.conf`.

```
winbind use default domain = true
```

If users must specify the domain name to log in, you must set the `SSOUserFormat` option on the Linux desktop. For more information, see [“Setting Options in Configuration Files on a Linux Desktop,”](#) on page 47. Be aware that SSO always uses the short domain name in upper case. For example, if the domain is `mydomain.com`, SSO will use `MYDOMAIN` as the domain name. Therefore, you must specify `MYDOMAIN` when setting the `SSOUserFormat` option. Regarding short and long domain names, the following rules apply:

- For OpenLDAP, you must use short domain names in upper case.
- Winbind supports both long and short domain names.

AD supports special characters in login names but Linux does not. Therefore, do not use special characters in login names when setting up SSO.

In AD, if a user's `UserPrincipalName` (UPN) attribute and `sAMAccount` attribute do not match and the user logs in with the UPN, SSO will fail. The workaround is for the user to log in using the name that is stored in `sAMAccount`.

View does not require the user name to be case-sensitive. You must ensure that the Linux operating system can handle case-insensitive user names.

- For Winbind, the user name is case-insensitive by default.
- For OpenLDAP, Ubuntu uses NSCD to authenticate users and is case-insensitive by default. RHEL and CentOS use SSSD to authenticate users and the default is case-sensitive. To change the setting, edit the file `/etc/sss/sss.conf` and add the following line in the `[domain/default]` section:

```
case_sensitive = false
```

For Ubuntu 16.04 or 14.04, configure `UseGnomeFlashback=TRUE` in the `/etc/vmware/viewagent-custom.conf` file to use the GNOME Flashback (Metacity) desktop environment.

## Smart Card Redirection

To set up smart card redirection, first follow the instructions from the Linux distributor and from the smart card vendor. Then update the `pcsc-lite` package to 1.7.4. For example, run the following commands:

```
#yum groupinstall "Development tools"
#yum install libudev-devel
#service pcscd stop
#wget https://alioth.debian.org/frs/download.php/file/3598/pcsc-lite-1.7.4.tar.bz2
#tar -xjvf pcsc-lite-1.7.4.tar.bz2
#cd ./pcsc-lite-1.7.4
#./configure --prefix=/usr/ --libdir=/usr/lib64/ --enable-usbdropdir=/usr/lib64/pcsc/drivers
--enable-confdir=/etc --enable-ipcdire=/var/run --disable-libusb --disable-serial --disable-usb
--disable-libudev
#make
#make install
#service pcscd start
```

For Winbind, add the following statement to the configuration file `/etc/samba/smb.conf`.

```
winbind use default domain = true
```

When you install the Horizon Agent, you must first disable SELinux or enable permissive mode for SELinux. You must also specifically select the smart card redirection component because the component is not selected by default. For more information, see [“install\\_viewagent.sh Command-Line Options,”](#) on page 42.

Smartcard SSO is enabled in Horizon View 7.0.1 or later. In addition, if the smart card redirection feature is installed on a virtual machine, vSphere Client's USB redirection does not work with the smart card.

Smart card redirection supports only one smart card reader. This feature does not work if two or more readers are connected to the client device.

Smart card redirection supports only one certificate on the card. If more than one certificate is on the card, the one in the first slot is used and the others are ignored. This is a Linux limitation.

---

### NOTE

- Smartcard supports the following winbind value. Else the smartcard SSO and manual login fails.

```
winbind use default domain=true
```

- When you use Linux client to authenticate the broker with PIV card, which is supported by Linux desktop smartcard redirection, you must add `view.sslProtocolString = "TLSv1.1"` configuration for the Linux client at `~/vmware/view-preferences` to avoid SSL error.
-



# Setting Up Graphics for Linux Desktops

# 4

You can configure the currently supported RHEL distributions to take advantage of NVIDIA capabilities on ESXi host or on a guest operating system.

## VM Clone Requirements for Setting Up 3D Graphics

You must consider the following requirements for VM Clone before setting up 3D graphics.

- For vGPU and vSGA, complete the graphic setup in the base VM. Clone the VMs. The graphic settings work for cloned VMs and no further settings are required.
- For vDGA, complete the graphic setup in the base VM. Clone the VMs. However before you power on the cloned VMs, you must remove the existing NVIDIA pass-through PCI device from the cloned VM and add the new NVIDIA pass-through PCI device to the cloned VM. NVIDIA pass-through PCI device cannot be shared between VMs. Each VM uses a dedicated NVIDIA pass-through PCI device.

This chapter includes the following topics:

- [“Configure Supported RHEL Distributions for vGPU,”](#) on page 29
- [“Configure RHEL 6 for vDGA,”](#) on page 34
- [“Configure RHEL 7 for vSGA,”](#) on page 37

## Configure Supported RHEL Distributions for vGPU

You can set up a supported RHEL distribution to take advantage of NVIDIA vGPU (shared GPU hardware acceleration) capabilities on the ESXi host.

You must use the NVIDIA Linux VM display driver that matches the ESXi host GPU driver(.vib). See the NVIDIA Web site for information about driver packages.

---

**IMPORTANT** NVIDIA vGPU is supported on NVIDIA Maxwell M60 graphics cards and NVIDIA M6 graphics cards. This feature does not work on other NVIDIA graphics cards such as GRID K1 or K2.

---



**CAUTION** Before you begin, verify that Horizon Agent is not installed on the Linux virtual machine. If you install Horizon Agent before you configure the machine to use NVIDIA vGPU, required configuration parameters in the `xorg.conf` file are overwritten, and NVIDIA vGPU does not work. You must install Horizon Agent after the NVIDIA vGPU configuration is completed.

---

## Install the VIB for the NVIDIA GRID vGPU Graphics Card on the ESXi Host

You must download and install the VIB for your NVIDIA GRID graphics card on the ESXi 6.0 U1 or later host.

NVIDIA provides a vGPU software package that includes a vGPU Manager, which you install on the ESXi host in this procedure, and a Linux Display Driver, which you will install on the Linux virtual machine in a later procedure.

### Prerequisites

- Verify that vSphere 6.0 U1 or a later release is installed in your environment.
- Verify that the NVIDIA Maxwell M60 GPUs or M6 GPUs are installed on the ESXi host.

### Procedure

- 1 Download the VIB for your NVIDIA GRID vGPU graphics card from the [NVIDIA Driver Downloads](#) site.

Select the appropriate VIB version from the drop-down menus.

Option	Description
<b>Product Type</b>	<b>GRID</b>
<b>Product Series</b>	Select <b>NVIDIA GRID vGPU</b> .
<b>Product</b>	Select the version (such as <b>GRID K2</b> ) that is installed on the ESXi host.
<b>Operating System</b>	Select the VMware vSphere ESXi version.

- 2 Uncompress the vGPU software package .zip file.
- 3 Upload the vGPU Manager folder to the ESXi 6.0 U1 host.

---

**NOTE** You will install the Linux Display Driver on the Linux virtual machine in a later procedure.

---

- 4 Power off or suspend all virtual machines on the ESXi host.
- 5 Connect to the ESXi host using SSH.
- 6 Stop the xorg service.

```
# /etc/init.d/xorg stop
```

- 7 Install the NVIDIA VIB.

For example:

```
# esxcli system maintenanceMode set --enable true
# esxcli software vib install -v /path-to-vib/NVIDIA-VIB-name.vib
# esxcli system maintenanceMode set --enable false
```

- 8 Reboot or update the ESXi host.

- ◆ For an installed ESXi host, reboot the host.
- ◆ For a stateless ESXi host, take the following steps to update the host. (These steps also work on an installed host.)

```
Update vmkdevmgr:
# kill -HUP $(cat /var/run/vmware/vmkdevmgr.pid)
```

```
Wait for the update to complete:
# localcli --plugin-dir /usr/lib/vmware/esxcli/int deviceInternal bind
```

```
This is a new requirement with the NVIDIA 352.* host driver:
# /etc/init.d/nvidia-vgpu start
```

```
Restart xorg, which is used for GPU assignment:
# /etc/init.d/xorg start
```

- 9 Verify that the xorg service is running after the host is restarted.

## Configure a Shared PCI Device for vGPU on the Linux Virtual Machine

To use NVIDIA vGPU, you must configure a shared PCI device for the Linux virtual machine.

### Prerequisites

- Verify that the Linux virtual machine is prepared for use as a desktop. See [“Create a Virtual Machine and Install Linux,”](#) on page 19 and [“Prepare a Linux Machine for Remote Desktop Deployment,”](#) on page 20.
- Verify that Horizon Agent is not installed on the Linux virtual machine.
- Verify that the NVIDIA VIB is installed on the ESXi host. See [“Install the VIB for the NVIDIA GRID vGPU Graphics Card on the ESXi Host,”](#) on page 30.
- Familiarize yourself with the virtual GPU types that are available with NVIDIA vGPU, which you select with the **GPU Profile** setting. The virtual GPU types provide varying capabilities on the physical GPUs installed on the ESXi host. See [“NVIDIA Virtual GPU Types,”](#) on page 31.

### Procedure

- 1 Power off the virtual machine.
- 2 In vSphere Web Client, select the virtual machine and, under the **VM Hardware** tab, click **Edit Settings**.
- 3 In the **New device** menu, select **Shared PCI Device**.
- 4 Click **Add** and select **NVIDIA GRID vGPU** from the drop-down menu.
- 5 For the **GPU Profile** setting, select a virtual GPU type from the drop-down menu.
- 6 Click **Reserve all memory** and click **OK**.

You must reserve all virtual machine memory to enable the GPU to support NVIDIA GRID vGPU.

- 7 Power on the virtual machine.

## NVIDIA Virtual GPU Types

With the **GPU Profiles** setting on the Virtual Hardware page in vSphere Web Client, you can select a virtual GPU type that provides specific capabilities on the physical NVIDIA GPU on the ESXi host.

On Linux virtual machines, NVIDIA GRID vGPU is supported on NVIDIA Maxwell M60 GPUs or NVIDIA M6 GPUs.

**Table 4-1.** Virtual GPU Types Available for NVIDIA GRID M60 vGPU on Linux Virtual Machines

Virtual GPU Type	Physical Board	Physical GPUs	FB Per Virtual GPU	Display Heads	Maximum Resolution	Maximum Virtual GPUs Per Physical GPU	Maximum Virtual GPUs Per Physical Board
GRID M60-0q	GRID M60	two	512M	2	2560x1600	16	32
GRID M60-1q	GRID M60	two	1G	2	2560x1600	8	16

**Table 4-1.** Virtual GPU Types Available for NVIDIA GRID M60 vGPU on Linux Virtual Machines (Continued)

Virtual GPU Type	Physical Board	Physical GPUs	FB Per Virtual GPU	Display Heads	Maximum Resolution	Maximum Virtual GPUs Per Physical GPU	Maximum Virtual GPUs Per Physical Board
GRID M60-2q	GRID M60	two	2G	4	2560x1600	4	8
GRID M60-4q	GRID M60	two	4G	4	3840x2160	2	4
GRID M60-8q	GRID M60	two	8G	4	3840x2160	1	2

**Table 4-2.** Virtual GPU Types Available for NVIDIA GRID M6 vGPU on Linux Virtual Machines

Virtual GPU Type	Physical Board	Physical GPUs	FB Per Virtual GPU	Display Heads	Maximum Resolution	Maximum Virtual GPUs Per Physical GPU	Maximum Virtual GPUs Per Physical Board
GRID M6-0q	GRID M6	one	512M	2	2560x1600	16	16
GRID M6-1q	GRID M6	one	1G	2	2560x1600	8	8
GRID M6-2q	GRID M6	one	2G	4	2560x1600	4	4
GRID M6-4q	GRID M6	one	4G	4	3840x2160	2	2
GRID M6-8q	GRID M6	one	8G	4	3840x2160	1	1

## Install the NVIDIA GRID vGPU Display Driver

To install the NVIDIA GRID vGPU display driver, you must disable the default NVIDIA driver, download the NVIDIA display drivers, and configure the PCI device on the virtual machine.

### Prerequisites

- Verify that you downloaded the vGPU software package from the NVIDIA download site, uncompressed the package, and have the Linux Display Driver (a package component) ready. See [“Install the VIB for the NVIDIA GRID vGPU Graphics Card on the ESXi Host,”](#) on page 30.

Also verify that a shared PCI device was added to the virtual machine. See [“Configure a Shared PCI Device for vGPU on the Linux Virtual Machine,”](#) on page 31

### Procedure

- Disable and blacklist the default NVIDIA Nouveau driver.
  - Edit the `grub.conf` or `grub` file.

For RHEL 6, the file is `/boot/grub/grub.conf`. For RHEL 7, the file is `/etc/default/grub`.

RHEL Version	Command
6	<code>sudo vi /boot/grub/grub.conf</code>
7	<code>sudo vi /etc/default/grub</code>

- Add the `rdblacklist=nouveau` line at the end of the kernel options.



- c Edit the `blacklist.conf` file.
 

```
sudo vi /etc/modprobe.d/blacklist.conf
```
- d Add the following line anywhere in the `blacklist.conf` file.
 

```
blacklist nouveau
```
- 2 Restart the virtual machine.
 

The display has a changed look and feel.
- 3 (Optional) Verify that the Nouveau driver is disabled.
 

```
/sbin/lsmmod | grep nouveau
```

If the `grep` search does not return any results, the Nouveau driver is disabled.
- 4 Copy the NVIDIA Linux Display Driver to the virtual machine.
- 5 Open a remote terminal to the virtual machine, or switch to a text console by typing `Ctrl-Alt-F2`, log in as `root`, and run the `init 3` command to disable X Windows.
- 6 Install additional components that are required for the NVIDIA driver.
 

```
sudo yum install gcc-c++
sudo yum install kernel-devel-$(uname -r)
sudo yum install kernel-headers-$(uname -r)
```
- 7 Add an executable flag to the NVIDIA GRID vGPU driver package.
 

```
chmod +x NVIDIA-Linux-x86_64-version-grid.run
```
- 8 Start the NVIDIA GRID vGPU installer.
 

```
sudo ./NVIDIA-Linux-x86_64-version-grid.run
```
- 9 Accept the NVIDIA software license agreement and select **Yes** to automatically update the X configuration settings.

### What to do next

Install Horizon Agent on the Linux virtual machine. See [“Install Horizon Agent on a Linux Virtual Machine,”](#) on page 41.

Create a desktop pool that contains the configured Linux virtual machines. See [“Create a Manual Desktop Pool for Linux,”](#) on page 57.

## Verify That the NVIDIA Display Driver Is Installed

You can verify that the NVIDIA display driver is installed on a RHEL 6 virtual machine by displaying the NVIDIA driver output in a View desktop session.

### Prerequisites

- Check that you installed the NVIDIA display driver.
- Verify that Horizon Agent is installed on the Linux virtual machine. See [“Install Horizon Agent on a Linux Virtual Machine,”](#) on page 41.
- Verify that the Linux virtual machine is deployed in a desktop pool. See [“Create a Manual Desktop Pool for Linux,”](#) on page 57.

**Procedure**

- 1 Restart the Linux virtual machine.

The Horizon Agent startup script initializes the X server and display topology.

You can no longer view the virtual machine display in the vSphere console.

- 2 From Horizon Client, connect to the Linux desktop.
- 3 In the Linux desktop session, verify that the NVIDIA display driver is installed.

Open a terminal window and run the `glxinfo | grep NVIDIA` command.

The NVIDIA driver output is displayed. For example:

```
[root]# glxinfo | grep NVIDIA
server glx vendor string: NVIDIA Corporation
client glx vendor string: NVIDIA Corporation
OpenGL vendor string: NVIDIA Corporation
OpenGL version string: 4.5.0 NVIDIA 346.47
OpenGL shading language version string: 4.50 NVIDIA
```

The user can access the NVIDIA graphics capabilities on the remote desktop.

After verifying the installation of NVIDIA display driver, perform the following tasks for installation to work correctly.

- If you upgrade the Linux kernel, Horizon Agent might not be able to communicate with View Connection Server. To resolve the problem, reinstall the NVIDIA driver.
- Set the NVIDIA GRID licensing in the Linux VM. See NVIDIA documentation for more information. Linux desktop will not work correctly if licensing is not set. For example, auto-fit will not work.

## Configure RHEL 6 for vDGA

You can set up an RHEL 6 guest operating system so that Horizon 7 for Linux desktop can take advantage of vDGA capabilities on the ESXi host.



**CAUTION** Before you begin, verify that Horizon Agent is not installed on the Linux virtual machine. If you install Horizon Agent before you configure the machine to use vDGA, required configuration parameters in the `xorg.conf` file are overwritten, and vDGA does not work. You must install Horizon Agent after the vDGA configuration is completed.

## Enable DirectPath I/O for NVIDIA GRID on a Host

Before you configure a Linux virtual machine to use vDGA, you must make the NVIDIA GRID GPU PCI devices available for DirectPath I/O passthrough on the ESXi host.

**Prerequisites**

- Verify that vSphere 6.0 or a later release is installed in your environment.
- Verify that the NVIDIA GRID K1 or K2 graphics cards are installed on the ESXi host.

**Procedure**

- 1 In the vSphere Web Client, browse to the ESXi host.
- 2 Click the **Manage** tab and click **Settings**.
- 3 In the Hardware section, click **PCI Devices**.

- To enable DirectPath I/O passthrough for the NVIDIA GRID GPUs, click **Edit**.

Icon	Description
Green icon	The PCI device is active and can be enabled.
Orange icon	The state of the device has changed. You must reboot the host before you can use the device.

- Select the NVIDIA GRID GPUs and click **OK**.  
The PCI devices are added to the table, DirectPath I/O PCI Devices Available to VMs.
- Reboot the host to make the PCI devices available for use by the Linux virtual machines.

## Add a vDGA Pass-Through Device to a RHEL 6 Virtual Machine

To configure a RHEL 6 virtual machine to use vDGA, you must add the PCI device to the virtual machine. With this step, the physical device on the ESXi host can be passed through for use on the virtual machine.

### Prerequisites

- Verify that the Linux virtual machine is prepared for use as a desktop. See [“Create a Virtual Machine and Install Linux,”](#) on page 19 and [“Prepare a Linux Machine for Remote Desktop Deployment,”](#) on page 20.
- Verify that Horizon Agent is not installed on the Linux virtual machine.
- Verify that the NVIDIA GRID GPU PCI device was made available for DirectPath I/O pass-through on the host. See [“Enable DirectPath I/O for NVIDIA GRID on a Host,”](#) on page 34.

### Procedure

- Log in to the RHEL 6 guest operating system as a local user configured with sudo rights.
- In vSphere Web Client, select the virtual machine and, under the **VM Hardware** tab, click **Edit Settings**.
- In the **New device** menu, select **PCI Device**.
- Click **Add** and select the PCI device from the drop-down menu.
- Click **Reserve all memory** and click **OK**.

You must reserve all virtual machine memory to enable the GPU to support vDGA.

- Power on the virtual machine and open vSphere console to connect to the machine.
- Verify that the NVIDIA GRID device is passed through to the virtual machine.

Open a terminal window and run the following command:

```
lspci | grep NVIDIA
```

The XX:00.0 VGA-compatible controller is displayed. For example:

```
NVIDIA Corporation GK104GL [GRID K2]
```

## Install the NVIDIA Display Driver for vDGA

To install the NVIDIA display driver for vDGA, you must disable the default NVIDIA driver, download the NVIDIA display drivers, and configure the PCI device on the virtual machine.

### Prerequisites

- Verify that the PCI device was added to the RHEL 6 virtual machine. See [“Add a vDGA Pass-Through Device to a RHEL 6 Virtual Machine,”](#) on page 35.

**Procedure**

- 1 Disable and blacklist the default NVIDIA Nouveau driver.

- a Edit the `grub.conf` file.

For RHEL 6, the file is `/boot/grub/grub.conf`.

RHEL Version	Command
6	<code>sudo vi /boot/grub/grub.conf</code>

- b Add the `rdblacklist=nouveau` line at the end of the kernel options.

- c Edit the `blacklist.conf` file.

`sudo vi /etc/modprobe.d/blacklist.conf`

- d Add the following line anywhere in the `blacklist.conf` file.

`blacklist nouveau`

- 2 Restart the virtual machine.

The display has a changed look and feel.

- 3 (Optional) Verify that the Nouveau driver is disabled.

`/sbin/lsmmod | grep nouveau`

If the `grep` search does not return any results, the Nouveau driver is disabled.

- 4 Download the NVIDIA driver from the [NVIDIA Driver Downloads](#) site.

Select the appropriate driver version from the NVIDIA drop-down menus:

Option	Description
<b>Product Type</b>	<b>GRID</b>
<b>Product Series</b>	<b>GRID Series</b>
<b>Product</b>	Select the version (such as <b>GRID K2</b> ) that is installed on the ESXi host.
<b>Operating System</b>	Linux 64-bit or Linux 32-bit

- 5 Open a remote terminal to the virtual machine, or switch to a text console by typing `Ctrl-Alt-F2`, log in as root, and run the `init 3` command to disable X Windows.

- 6 Install additional components that are required for the NVIDIA driver.

```
sudo yum install gcc-c++
sudo yum install kernel-devel-$(uname -r)
sudo yum install kernel-headers-$(uname -r)
```

- 7 Add an executable flag to the NVIDIA driver package for vDGA.

`chmod +x NVIDIA-Linux-x86_64-version.run`

- 8 Start the NVIDIA installer.

`sudo ./NVIDIA-Linux-x86_64-version.run`

- 9 Accept the NVIDIA software license agreement and select **Yes** to automatically update the X configuration settings.

**What to do next**

Install Horizon Agent on the Linux virtual machine. See [“Install Horizon Agent on a Linux Virtual Machine,”](#) on page 41.

Create a desktop pool that contains the configured Linux virtual machines. See [“Create a Manual Desktop Pool for Linux,”](#) on page 57.

## Verify That the NVIDIA Display Driver Is Installed

You can verify that the NVIDIA display driver is installed on a RHEL 6 virtual machine by displaying the NVIDIA driver output in a View desktop session.

### Prerequisites

- Check that you installed the NVIDIA display driver.
- Verify that Horizon Agent is installed on the Linux virtual machine. See [“Install Horizon Agent on a Linux Virtual Machine,”](#) on page 41.
- Verify that the Linux virtual machine is deployed in a desktop pool. See [“Create a Manual Desktop Pool for Linux,”](#) on page 57.

### Procedure

- 1 Restart the Linux virtual machine.

The Horizon Agent startup script initializes the X server and display topology.

You can no longer view the virtual machine display in the vSphere console.

- 2 From Horizon Client, connect to the Linux desktop.
- 3 In the Linux desktop session, verify that the NVIDIA display driver is installed.

Open a terminal window and run the `glxinfo | grep NVIDIA` command.

The NVIDIA driver output is displayed. For example:

```
[root]# glxinfo | grep NVIDIA
server glx vendor string: NVIDIA Corporation
client glx vendor string: NVIDIA Corporation
OpenGL vendor string: NVIDIA Corporation
OpenGL version string: 4.5.0 NVIDIA 346.47
OpenGL shading language version string: 4.50 NVIDIA
```

The user can access the NVIDIA graphics capabilities on the remote desktop.

After verifying the installation of NVIDIA display driver, perform the following tasks for installation to work correctly.

- If you upgrade the Linux kernel, Horizon Agent might not be able to communicate with View Connection Server. To resolve the problem, reinstall the NVIDIA driver.
- Set the NVIDIA GRID licensing in the Linux VM. See NVIDIA documentation for more information. Linux desktop will not work correctly if licensing is not set. For example, auto-fit will not work.

## Configure RHEL 7 for vSGA

You can set up an RHEL 7 guest operating system so that a Horizon 7 for Linux desktop can take advantage of vSGA capabilities.

### Install the VIB for the NVIDIA Graphics Card for vSGA on the ESXi Host

You must download and install the VIB for your NVIDIA GRID graphics card on the ESXi 6.0 U1 or later host.

NVIDIA provides a VMware vSphere ESXi Driver for vSGA. For vSGA, an NVIDIA display driver is not installed on the Linux virtual machine.

**Prerequisites**

- Verify that vSphere 6.0 U1 or a later release is installed in your environment.
- Verify that NVIDIA driver is installed in your environment.
- Verify that the NVIDIA GRID K1 or K2 GPUs are installed on the ESXi host.

**Procedure**

- 1 Download the VIB for your NVIDIA GRID vGPU graphics card from the [NVIDIA Driver Downloads](#) site.

Select the appropriate VIB version from the drop-down menus.

Option	Description
<b>Product Type</b>	<b>GRID</b>
<b>Product Series</b>	Select <b>GRID Series</b> .
<b>Product</b>	Select the version (such as <b>GRID K2</b> ) that is installed on the ESXi host.
<b>Operating System</b>	Select the VMware vSphere ESXi version.

- 2 Upload the VMware vSphere ESXi Driver for vSGA to the ESXi 6.0 U1 host.
- 3 Power off or suspend all virtual machines on the ESXi host.
- 4 Connect to the ESXi host using SSH.

- 5 Stop the xorg service.

```
# /etc/init.d/xorg stop
```

- 6 Install the NVIDIA VIB.

For example:

```
# esxcli system maintenanceMode set --enable true
# esxcli software vib install -v /path-to-vib/NVIDIA-VIB-name.vib
# esxcli system maintenanceMode set --enable false
```

- 7 Restart xorg, which is used for GPU assignment:

```
# /etc/init.d/xorg start
```

- 8 Reboot the ESXi host.
- 9 Verify that the xorg service is running after the host is restarted.

**Configure 3D Capabilities for vSGA on the Linux Virtual Machine**

To configure a RHEL 7 virtual machine to use vSGA, you must configure 3D settings for the virtual machine's video card in vSphere Web Client.

**Prerequisites**

- Verify that the Linux virtual machine is prepared for use as a desktop, Horizon Agent is installed, and the machine is deployed in a desktop pool.
- Verify that the NVIDIA VIB is installed on the ESXi host. See [“Install the VIB for the NVIDIA Graphics Card for vSGA on the ESXi Host,”](#) on page 37.

**Procedure**

- 1 Power off the virtual machine.
- 2 In vSphere Web Client, select the virtual machine and, under the **VM Hardware** tab, click **Edit Settings**.

- 3 In the Virtual Hardware tab, click **Video card** to expand the menu settings.
- 4 Set the **Total video memory** to 128 MB.
- 5 For **3D Graphics**, select **Enable 3D Support**.
- 6 For **3D Renderer**, select **Hardware** from the drop-down menu.
- 7 For **3D Memory**, select a suitable value for your application requirements.  
If your users connect to more than 3 monitors, set this value to at least 1024 MB.
- 8 Click **OK**.
- 9 Power on the virtual machine.

### What to do next

Verify that vSGA is running on the Linux virtual machine.

Next, install Horizon Agent on the Linux virtual machine. See [“Install Horizon Agent on a Linux Virtual Machine,”](#) on page 41.

## Verify that vSGA is Running on a Linux Virtual Machine

You can verify that vSGA is running on a RHEL 7 virtual machine by checking the virtual machine log file and checking the guest operating system.

### Procedure

- 1 Open the `vmware.log` file for the virtual machine.

If a supported GPU and NVIDIA VIB are installed correctly, the log file displays lines such as those in the following example:

```
2015-06-24T22:19:25.259Z| mks| I120: OpenGL Version: "4.0.0 NVIDIA 346.69" (4.0.0)
2015-06-24T22:19:25.259Z| mks| I120: GLSL Version: "4.00 NVIDIA" (4.00.0)
2015-06-24T22:19:25.259Z| mks| I120: OpenGL Vendor: "NVIDIA Corporation"
2015-06-24T22:19:25.259Z| mks| I120: OpenGL Renderer: "Quadro 4000/PCIe/SSE2"
```

If a supported GPU and NVIDIA VIB are not installed correctly, the virtual machine uses the Software Renderer. The `vmware.log` file displays lines such as those in the following example:

```
2015-07-06T17:09:26.423Z| vmx| I120: [msg.mks.noGPUResourceFallback] Hardware GPU resources
are not available. The virtual machine uses software rendering.
2015-07-06T17:09:26.423Z| vmx| I120: -----
2015-07-06T17:09:26.425Z| svga| I120: MKS-SWP: plugin started - llvmpipe (LLVM 3.3, 256 bits)
2015-07-06T17:09:26.426Z| svga| I120: Started Shim3D
2015-07-06T17:09:26.426Z| svga| I120: MKS-RenderMain: Starting SWRenderer
```

- 2 In the guest operating system on the virtual machine, type the following command.

```
glxinfo|grep Gallium
```

If vSGA is working, the command returns the following text:

```
OpenGL renderer string: Gallium 0.4 on SVGA3D; build : RELEASE;
```

If vSGA is not working correctly, the command returns the following text:

```
OpenGL renderer string: Gallium 0.4 on llvmpipe (LLVM 3.3, 256 bits)
```

### What to do next

Install Horizon Agent on the Linux virtual machine. See [“Install Horizon Agent on a Linux Virtual Machine,”](#) on page 41.





# Installing Horizon Agent

---

You must install Horizon Agent on the Linux desktops so that View Connection Server can communicate with and manage the desktops.

This chapter includes the following topics:

- [“Install Horizon Agent on a Linux Virtual Machine,”](#) on page 41
- [“Configure the Certificate for Linux Agent,”](#) on page 43
- [“Upgrading the Horizon Agent on a Linux Virtual Machine,”](#) on page 44
- [“Uninstall Horizon 7 for Linux Machines,”](#) on page 46

## Install Horizon Agent on a Linux Virtual Machine

You must install Horizon Agent on a Linux virtual machine before you can deploy the machine as a remote desktop.

Beginning with Horizon 7.0.1 release, Horizon Agent for Linux uses vCenter managed virtual machines. The managed virtual machines provide the following enhancements.

- vCenter is a mandatory requirement for Linux desktop deployment.
- Horizon Agent installation on Linux does not require registration.
- For a large number of Linux desktop deployment, you can install the Horizon Agent on the base virtual machine.



**CAUTION** If you intend to use NVIDIA GRID vGPU, vDGA, or vSGA, you must configure these 3D features on the Linux virtual machine before you install Horizon Agent. If you install Horizon Agent first, required parameters in the `xorg.conf` file are overwritten, and the 3D graphics features do not work.

See [“Configure Supported RHEL Distributions for vGPU,”](#) on page 29, [“Configure RHEL 6 for vDGA,”](#) on page 34, or [“Configure RHEL 7 for vSGA,”](#) on page 37. Install Horizon Agent after the 3D graphics configuration is completed.

For 2D graphics configuration, you can install Horizon Agent after you complete the steps in [“Prepare a Linux Machine for Remote Desktop Deployment,”](#) on page 20.

---

### Prerequisites

- Verify that the Linux guest operating system is prepared for desktop use. See [“Prepare a Linux Machine for Remote Desktop Deployment,”](#) on page 20.
- Familiarize yourself with the Horizon Agent installer script for Linux. See [“install\\_viewagent.sh Command-Line Options,”](#) on page 42.

**Procedure**

- 1 Download the Horizon Agent for Linux installer file from the VMware download site at <https://my.vmware.com/web/vmware/downloads>.  
 Under Desktop & End-User Computing, select the VMware Horizon 7 download, which includes the Horizon Agent for Linux installer.  
 The installer filename is `VMware-horizonagent-linux-x86_64-y.y.y-xxxxxxx.tar.gz` for 64-bit Linux where `y.y.y` is the version number and `xxxxxxx` is the build number.
- 2 Unpack the tarball for your Linux distribution on the guest operating system.  
 For example:  

```
tar -xzf <View Agent tar ball>
```
- 3 Navigate to the tar ball folder.
- 4 Run the `install_viewagent.sh` script as superuser.  
 See “[install\\_viewagent.sh Command-Line Options](#),” on page 42 for a list of the command line options.  
 For example:  

```
sudo ./install_viewagent.sh
```
- 5 Type **Yes** to accept the EULA if you run `install_viewagent.sh` without specifying the `-A` option.  
 The installer does not run unless you accept the EULA.
- 6 Reboot Linux for the changes to take effect.

After installation, the `viewagent` service is started. Verify that the service is started using `sudo service viewagent status`.

**What to do next**

Deploy the virtual machine in a desktop pool. See “[Create a Manual Desktop Pool for Linux](#),” on page 57.

**install\_viewagent.sh Command-Line Options**

The `install_viewagent.sh` script installs Horizon Agent on a Linux guest operating system.

Use the following form of the `install_viewagent.sh` script in a command window in the gnome desktop environment.

```
install_viewagent.sh command_option argument [command_option argument] . . .
```

The `install_viewagent.sh` script includes mandatory and optional parameters.

**Table 5-1.** `install_viewagent.sh` Optional but Required Parameter

Optional Parameter (Required Information)	Description
-A yes no	Accept or Refuse EULA. You must specify <b>yes</b> for the install to proceed.

**Table 5-2.** `install_viewagent.sh` Optional Parameters

Optional Parameters	Description
-a yes no	-a yes no
-f yes no	Install or bypass support of the Federal Information Processing Standards (FIPS) 140-2. Default is <b>no</b> .

**Table 5-2.** `install_viewagent.sh` Optional Parameters (Continued)

Optional Parameters	Description
-j	JMS SSL keystore password. By default, installer generates a random string.
-m yes no	Install or bypass the smart card redirection support. Default is <b>no</b> .
-r yes no	Restart the system automatically after installation. Default is <b>no</b> .
-s	Self signed cert subject DN. By default, installer uses Blast.
-C yes no	Install or bypass Clipboard Redirection support. Default is <b>yes</b> .
-F yes no	Install or bypass CDR support. Default is <b>yes</b> .
-M yes no	Upgrade the Linux Agent to managed or unmanaged agent. Default is <b>yes</b> .
-S yes no	Install or bypass Single Sign-On (SSO) support. Default is <b>yes</b> .
-U yes no	Install or bypass USB support. Default is <b>no</b> .

**Table 5-3.** Examples of `install_viewagent.sh` Parameters

Condition	Examples
Fresh Installation	<b>sudo ./install_viewagent.sh -A yes</b> Fresh installation always requires a new desktop pool creation.
Upgrade from an unmanaged virtual machine and retain the unmanaged virtual machine style	<b>sudo ./install_viewagent.sh -A yes -M no</b> This type of upgrade does not require a new desktop pool creation. You can reuse the existing desktop pool. <b>NOTE</b> To ensure the best possible performance, do not use an unmanaged virtual machine.
Upgrade from an unmanaged virtual machine deployment and convert to a managed virtual machine style. The upgrade requires new desktop pool creation on broker	<b>sudo ./install_viewagent.sh -A yes</b> This type of upgrade requires a new desktop pool creation. You must delete the existing desktop pool.

## Configure the Certificate for Linux Agent

When you install Linux Agent, the installer generates a self-signed certificate for VMwareBlastServer.

- When the Blast Security Gateway is disabled on the broker, VMwareBlastServer presents this certificate to the browser that uses HTML Access to connect to the Linux Desktop.
- When the Blast Security Gateway is enabled on the broker, Blast Security Gateway's certificate presents the certificate to the browser.

To comply with industry or security regulations, you can replace the self-signed certificate with a certificate that is signed by a Certificate Authority (CA).

**Procedure**

- 1 Install the private key and the certificate to VMwareBlastServer.
  - a Rename the private key to rui.key and the certificate to rui.crt .
  - b Run `sudo chmod 550 /etc/vmware/ssl`.
  - c Copy the rui.crt and rui.key to /etc/vmware/ssl.
  - d Run `chmod 440 /etc/vmware/ssl`.
- 2 Install the root and intermediate Certificate Authority into the Linux OS Certificate Authority store.

---

**NOTE** Check your Linux distribution documentation for the Linux system settings change.

---

## Upgrading the Horizon Agent on a Linux Virtual Machine

You can upgrade Horizon Agent on a Linux virtual machine by installing the latest version of Horizon Agent.

Unmanaged virtual machine: The agent installer registers the virtual machine to the broker which requires broker admin information. The Desktop Pool Creation wizard uses **Other Sources** in the Machine Source page to select the registered virtual machine.

Managed virtual machine: The installer does not communicate with the broker. The Desktop Pool Creation wizard uses **vCenter virtual machines** in the Machine Source page to select the virtual machines through vCenter. The managed virtual machine deployment supports the following functions.

- Remote Machine Power Policy
- Allow users to reset their machines

---

**NOTE** Horizon Agent for Linux 7.0.0 and earlier versions functioned as unmanaged virtual machines. The Horizon Agent for Linux 7.0.1 functions as managed virtual machine support.

---

You can use the following methods to upgrade from unmanaged to a managed virtual machine deployment.

- Retain the unmanaged virtual machine deployment and upgrade to the required version. This type of upgrade does not require any configuration modifications in View Connection Server.
- Upgrade from an unmanaged virtual machine deployment to a managed virtual machine deployment to any version. This type of upgrade requires a new desktop pool creation on the View Connection Server.

---

**NOTE** For the upgrade from a managed virtual machine deployment, you can retain the managed virtual machine deployment and upgrade to the required version. However, to convert the managed virtual machine deployment to an unmanaged virtual machine deployment during an upgrade is not supported.

---

The following parameters are available for upgrade.

Parameter	Description
-a yes no	-a yes no
-f yes no	Install or bypass support of the Federal Information Processing Standards (FIPS) 140-2. Default is <b>no</b> .
-m yes no	Install or bypass the smart card redirection support. Default is <b>no</b> .
-r yes no	Reboot the operating system after installation. The default is <b>no</b> .
-A yes	EULA acceptance. You must specify <b>yes</b> for the install to proceed. If this parameter is not specified, the install script prompts for the value.
-C yes no	Install or bypass Clipboard Redirection support. Default is <b>yes</b> .

Parameter	Description
-F yes no	Install or bypass CDR support. Default is <b>yes</b> .
-M yes no	Upgrade the Linux Agent to managed unmanaged agent. The default value is <b>yes</b> .
-S yes no	Install or bypass SingleSignOn (SSO) support. Default is <b>yes</b> .
-U yes no	Install or Bypass USB support. Default is <b>no</b> .

## Upgrade Horizon Agent on a Linux Virtual Machine

You can upgrade Horizon Agent on a Linux machine by installing the latest version of Horizon Agent..

### Prerequisites

- Verify that the `VMwareBlastServer` process is not running.

To stop this process, ensure that the user logs off the machine and no desktop session is active, or reboot the machine.

### Procedure

- 1 Download the latest Horizon Agent for Linux installer file from the VMware download site at <https://my.vmware.com/web/vmware/downloads>.

Under Desktop & End-User Computing, select the VMware Horizon 7 download, which includes the Horizon Agent for Linux installer.

The installer filename is `VMware-viewagent-linux-x86_64-y.y.y-xxxxxxx.tar.gz` for 64-bit Linux where `y.y.y` is the version number and `xxxxxxx` is the build number.

- 2 Unpack the tarball for your Linux distribution on the guest operating system.

For example:

```
tar -xzvf <View Agent tar ball>
```

- 3 Navigate to the tar ball folder.
- 4 Run the `install_viewagent.sh` script to upgrade unmanaged virtual machines using one of the following deployment scenarios:

Option	Description
<b>Upgrade an unmanaged virtual machine deployment and retain the unmanaged virtual machine deployment</b>	<code>sudo ./install_viewagent.sh -A yes -M no</code> <b>NOTE</b> To ensure the best possible performance, do not use an unmanaged virtual machine.
<b>Upgrade an unmanaged virtual machine deployment and change it to managed virtual machine deployment</b>	<code>sudo ./install_viewagent.sh -A yes -M yes</code> <b>NOTE</b> In View Administrator, delete the existing desktop pool for unmanaged virtual machine deployment and create a new desktop pool for managed virtual machine deployment. For more info, see <a href="#">“Create a Manual Desktop Pool for Linux,”</a> on page 57.
<b>Upgrade a managed virtual machine deployment</b>	<code>sudo ./install_viewagent.sh -A yes -M yes</code> <b>NOTE</b> After upgrading, your existing desktop pool can be reused.

## Uninstall Horizon 7 for Linux Machines

To uninstall Horizon 7 for Linux on a virtual machine, you must uninstall Horizon Agent and remove configuration files.

### Prerequisites

Verify that the VMwareBlastServer process is not running. To stop this process, ensure that you log off the machine and no desktop session is active, or reboot the machine.

### Procedure

- 1 Open a terminal window on the virtual machine and run the Horizon Agent uninstall script.

```
sudo /usr/lib/vmware/viewagent/bin/uninstall_viewagent.sh
```

The script stops the Horizon Agent processes, deletes the Horizon Agent service and software from installation directory `/usr/lib/vmware/viewagent`.

- 2 Manually delete the Horizon 7 for Linux configuration files at `/etc/vmware` directory.

# Configuration Options for Linux Desktops

# 6

You can configure various options to customize the user experience using configuration files.

This chapter includes the following topics:

- [“Setting Options in Configuration Files on a Linux Desktop,”](#) on page 47
- [“Example Blast Settings for Linux Desktops,”](#) on page 54
- [“Examples of Client Drive Redirection Options for Linux Desktops,”](#) on page 55
- [“Suppress the vSphere Console Display of a Linux Desktop,”](#) on page 55

## Setting Options in Configuration Files on a Linux Desktop

You can configure certain options by adding entries to the files `/etc/vmware/config` or `/etc/vmware/viewagent-custom.conf`.

During the installation of View Agent or Horizon Agent, the installer copies two configuration template files, `config.template` and `viewagent-custom.conf.template`, to `/etc/vmware`. In addition, if the files `/etc/vmware/config` and `/etc/vmware/viewagent-custom.conf` do not exist, the installer copies `config.template` to `config` and `viewagent-custom.conf.template` to `viewagent-custom.conf`. In the template files, all the configuration options are listed and documented. To set an option, simply remove the comment and change the value as appropriate.

For example, the following line in `/etc/vmware/config` enables the lossless PNG mode.

```
RemoteDisplay.alwaysLossless=TRUE
```

After you make configuration changes, reboot Linux for the changes to take effect.

### Configuration Options in `/etc/vmware/config`

VMwareBlastServer and its related plug-ins use the configuration file `/etc/vmware/config`.

---

**NOTE** The following table includes description for each agent-enforced policy setting for USB in the Horizon Agent configuration file. Horizon Agent uses the settings to decide if a USB can be forwarded to the host machine. Horizon Agent also passes the settings to Horizon Client for interpretation and enforcement according to whether you specify the `merge(m)` modifier to apply the Horizon Agent filter policy setting in addition to the Horizon Client filter policy setting, or `override(o)` modifier to use the Horizon Agent filter policy setting instead of the Horizon Client filter policy setting.

---

**Table 6-1.** Configuration Options in `/etc/vmware/config`

Option	Value/Format	Default	Description
<code>RemoteDisplay.alwaysLossless</code>	true or false	false	Graphic applications, especially graphic design applications, require pixel-exact rendering of images in the client display of a Linux desktop. You can configure a lossless PNG mode for images and video playback that are generated on a Linux desktop and rendered on the client device. This feature uses additional bandwidth between the client and the ESXi host.
<code>mksVNCServer.useUIInputButtonMapping</code>	true or false	false	Set this option to enable the support of a left-handed mouse on Ubuntu or RHEL 7. CentOS and RHEL 6 support a left-handed mouse and you do not need to set this option.
<code>RemoteDisplay.allowAudio</code>	true or false	true	Set this option to enable/disable audio out.
<code>VVC.ScRedir.Enable</code>	true or false	true	Set this option to enable/disable smart card redirection.
<code>VVC.logLevel</code>	fatal error, warn, info, debug, or trace	info	Use this option to set the log level of the VVC proxy node.
<code>VVC.RTAV.Enable</code>	true or false	true	Set this option to enable/disable audio input.
<code>Clipboard.Direction</code>	0, 1, 2, or 3	2	This option determines the clipboard redirection policy. <ul style="list-style-type: none"> <li>■ 0 - Disable clipboard redirection.</li> <li>■ 1 - Enable clipboard redirection in both directions.</li> <li>■ 2 - Enable clipboard redirection from client to remote desktop only.</li> <li>■ 3 - Enable clipboard redirection from remote desktop to client only.</li> </ul>
<code>cdrserver.logLevel</code>	error, warn, info, debug, trace or verbose	info	Use this option to set the log level for <code>vmware-CDRserver.log</code>
<code>cdrserver.forcedByAdmin</code>	true or false	false	Set this option to prevent or allow the client from sharing additional folders that are not specified with the <code>cdrserver.shareFolders</code> option.
<code>cdrserver.sharedFolders</code>	<i>file_path1,R;file_path2,;file_path3,R;...</i>	undefined	Specify one or more file paths to the folders that the client can share with the Linux desktop. For example: <ul style="list-style-type: none"> <li>■ for a Windows client: <b>C:\spreadsheets,;D:\ebooks,R</b></li> <li>■ for non-Windows client: <b>/tmp/spreadsheets;/tmp/ebooks,;/home/finance,R</b></li> </ul>



**Table 6-1.** Configuration Options in `/etc/vmware/config` (Continued)

Option	Value/Format	Default	Description
<code>cdrserver.permissions</code>	R	RW	<p>Use this option to apply additional read/write permissions that Horizon Agent has on the folders shared by Horizon Client. For example:</p> <ul style="list-style-type: none"> <li>■ If the folder shared by Horizon Client has read and write permissions and you set <code>cdrserver.permissions=R</code>, then Horizon Agent only has read access permissions.</li> <li>■ If the folder shared by Horizon Client only has read permissions and you set <code>cdrserver.permissions=RW</code>, Horizon Agent will still have read access rights only. Horizon Agent can not change the read only attribute that was set by Horizon Client. The only thing Horizon Agent can do is remove the write access rights</li> </ul> <p>Typical usages are:</p> <ul style="list-style-type: none"> <li>■ <code>cdrserver.permissions=R</code></li> <li>■ <code>#cdrserver.permissions=R</code> (i.e. comment it out or delete the entry)</li> </ul>
<code>cdrserver.cacheEnable</code>	true or false	true	Set this option to enable or disable the write caching feature from the agent towards the client side.
<code>UsbRedirPlugin.log.logLevel</code>	error, warn, info, debug, trace, or verbose	info	Use this option to set the log level for the USB Redirection plugin.
<code>UsbRedirServer.log.logLevel</code>	error, warn, info, debug, trace, or verbose	info	Use this option to set the log level for the USB Redirection server.
<code>viewusb.AllowAutoDeviceSplitting</code>	<code>{m o}:</code> <code>{true false}</code>	undefined, which equates to false	Set this option to allow or disallow the automatic splitting of composite USB devices. Example: <code>m:true</code>
<code>viewusb.SplitExcludeVidPid</code>	<code>{m o}:vid-xxx1_pid-yyy1[;vid-xxx2_pid-yyy2;...]</code>	undefined	Use this option to exclude or include a specified composite USB device from splitting by Vendor and Product IDs. The format of the setting is <code>vid-xxx1_pid-yyy1[;vid-xxx2_pid-yyy2;...]</code> . You must specify ID numbers in hexadecimal. You can use the wildcard character (*) in place of individual digits in an ID. Example: <code>m:vid-0f0f_pid-55**</code>

**Table 6-1.** Configuration Options in `/etc/vmware/config` (Continued)

Option	Value/Format	Default	Description
<code>viewusb.SplitVidPid</code>	<code>{m o}: vid-xxxx_pid-yyyy([exintf:zz[;exintf:ww]]z[;...])</code>	undefined	<p>Set this option to treat the components of a composite USB device specified by Vendor and Product IDs as separate devices. The format of the setting is <b>vid-xxxx_pid-yyyy(exintf:zz[;exintf:ww])</b></p> <p>You can use the <b>exintf</b> keyword to exclude components from redirection by specifying their interface number. You must specify ID numbers in hexadecimal, and interface numbers in decimal including any leading zero. You can use the wildcard character (*) in place of individual digits in an ID.</p> <p>Example:  <b>o:vid-0f0f_pid-***(exintf-01);vid-0781_pid-554c(exintf:01;exintf:02)</b></p> <p><b>NOTE</b>  Horizon does not automatically include the components that you have not explicitly excluded. You must specify a filter policy such as <b>Include VidPid Device</b> to include those components.</p>
<code>viewusb.AllowAudioIn</code>	<code>{m o}: {true false}</code>	undefined, which equates to <code>true</code>	Use this option to allow or disallow audio input devices to be redirected. Example: <b>o:false</b>
<code>viewusb.AllowAudioOut</code>	<code>{m o}: {true false}</code>	undefined, which equates to <code>false</code>	Set this option to allow or disallow redirection of audio output devices.
<code>viewusb.AllowHIDBootable</code>	<code>{m o}: {true false}</code>	undefined, which equates to <code>true</code>	Use this option to allow or disallow the redirection of input devices other than keyboards or mice that are available at boot time, also known as HID-bootable devices.
<code>viewusb.AllowDevDescFailsafe</code>	<code>{m o}: {true false}</code>	undefined, which equates to <code>false</code>	Set this option to allow or disallow devices to be redirected even if the Horizon Client fails to get the configuration or device descriptors. To allow a device even if it fails to get the configuration or device descriptors, include it in the Include filters, such as <b>IncludeVidPid</b> or <b>IncludePath</b> .
<code>viewusb.AllowKeyboardMouse</code>	<code>{m o}: {true false}</code>	undefined, which equates to <code>false</code>	Use this option to allow or disallow the redirection of keyboards with integrated pointing devices (such as a mouse, trackball, or touch pad).
<code>viewusb.AllowSmartcard</code>	<code>{m o}: {true false}</code>	undefined, which equates to <code>false</code>	Set this option to allow or disallow smart-card devices to be redirected.
<code>viewusb.AllowVideo</code>	<code>{m o}: {true false}</code>	undefined, which equates to <code>true</code>	Use this option to allow or disallow video devices to be redirected.
<code>viewusb.DisableRemoteConfig</code>	<code>{m o}: {true false}</code>	undefined, which equates to <code>false</code>	Set this option to disable or enable the use of Horizon Agent settings when performing USB device filtering.

**Table 6-1.** Configuration Options in `/etc/vmware/config` (Continued)

Option	Value/Format	Default	Description
<code>viewusb.ExcludeAllDevices</code>	<code>{true false}</code>	undefined, which equates to <code>false</code>	Use this option to exclude or include all USB devices from being redirected. If set to <b>true</b> , you can use other policy settings to allow specific devices or families of devices to be redirected. If set to <b>false</b> , you can use other policy settings to prevent specific devices or families of devices from being redirected. If you set the value of <b>ExcludeAllDevices</b> to <b>true</b> on Horizon Agent, and this setting is passed to Horizon Client, the Horizon Agent setting overrides the Horizon Client setting.
<code>viewusb.ExcludeFamily</code>	<code>{m o}:family_name_1[;family_name_2;...]</code>	undefined	Use this option to exclude families of devices from being redirected. For example: <b>m:bluetooth;smart-card</b> If you have enabled automatic device splitting, Horizon examines the device family of each interface of a composite USB device to decide which interfaces should be excluded. If you have disabled automatic device splitting, Horizon examines the device family of the whole composite USB device. <b>NOTE</b> However, mice and keyboards are excluded from redirection by default and do not need to be excluded with this setting.
<code>viewusb.ExcludeVidPid</code>	<code>{m o}:vid-xxx1_pid-yyy1[;vid-xxx2_pid-yyy2;...]</code>	undefined	Set this option to exclude devices with specified vendor and product IDs from being redirected. You must specify ID numbers in hexadecimal. You can use the wildcard character (*) in place of individual digits in an ID. For example: <b>o:vid-0781_pid-****;vid-0561_pid-554c</b>
<code>viewusb.ExcludePath</code>	<code>{m o}:bus-x1[/y1].../port-z1[;bus-x2[/y2].../port-z2;...]</code>	undefined	Use this option to exclude devices at specified hub or port paths from being redirected. You must specify bus and port numbers in hexadecimal. You cannot use the wildcard character in paths. For example: <b>m:bus-1/2/3_port-02;bus-1/1/1/4_port-ff</b>
<code>viewusb.IncludeFamily</code>	<code>{m o}:family_name_1[;family_name_2]...</code>	undefined	Set this option to include families of devices that can be redirected. For example: <b>o:storage; smart-card</b>
<code>viewusb.IncludePath</code>	<code>{m o}:bus-x1[/y1].../port-z1[;bus-x2[/y2].../port-z2;...]</code>	undefined	Use this option to include devices at specified hub or port paths that can be redirected. You must specify bus and port numbers in hexadecimal. You cannot use the wildcard character in paths. For example: <b>m:bus-1/2_port-02;bus-1/7/1/4_port-0f</b>
<code>viewusb.IncludeVidPid</code>	<code>{m o}:vid-xxx1_pid-yyy1[;vid-xxx2_pid-yyy2;...]</code>	undefined	Set this option to include devices with specified Vendor and Product IDs that can be redirected. You must specify ID numbers in hexadecimal. You can use the wildcard character (*) in place of individual digits in an ID. For example: <b>o:vid-***_pid-0001;vid-0561_pid-554c</b>
<code>mksVNCServer.useXExtButtonMapping</code>	<code>true</code> or <code>false</code>	<code>false</code>	Set this option to enable or disable the support of a left-handed mouse on SLED 11 SP3.

**Table 6-1.** Configuration Options in `/etc/vmware/config` (Continued)

Option	Value/Format	Default	Description
<code>mksvhan.clipboardSize</code>	An integer	1024	Use this option to specify the clipboard maximum size to copy and paste.
<code>RemoteDisplay.maxBandwidthKbps</code>	An integer	4096000	Specifies the maximum bandwidth in kilobits per second (kbps) for a VMware Blast session. The bandwidth includes all imaging, audio, virtual channel, and VMware Blast control traffic. The max value is 4 Gbps (4096000).
<code>RemoteDisplay.maxFPS</code>	An integer	60	Specifies the maximum rate of screen updates. Use this setting to manage the average bandwidth that users consume. Valid value should be between 3 and 60. The default is 60 updates per second.
<code>RemoteDisplay.enableStats</code>	true or false	false	Enable or Disable the Blast protocol statistics in mks log, such as bandwidth, FPS, RTT and so on.
<code>RemoteDisplay.allowH264</code>	true or false	true	Set this option to enable or disable H.264 Encoding.
<code>vdpservice.log.logLevel</code>	fatal error, warn, info, debug, or trace	info	Use this option to set the log level of the vdp service.
<code>RemoteDisplay.qpmaxH264</code>	available range of values: 0-51	36	Use this option to set the H264minQP quantization parameter, which specifies the best image quality for the remote display configured to use H.264 encoding. Set the value to greater than the value set for <code>RemoteDisplay.qpminH264</code> .
<code>RemoteDisplay.qpminH264</code>	available range of values: 0-51	10	Use this option to set the H264maxQP quantization parameter, which specifies the lowest image quality for the remote display configured to use H.264 encoding. Set the value to less than the value set for <code>RemoteDisplay.qpmaxH264</code> .
<code>RemoteDisplay.minQualityJPE G</code>	available range of values: 1-100	25	Specifies the image quality of the desktop display for JPEG/PNG encoding. The low-quality settings are for areas of the screen that change often, for example, when scrolling occurs.
<code>RemoteDisplay.midQualityJPE G</code>	available range of values: 1-100	35	Specifies the image quality of the desktop display for JPEG/PNG encoding. Use to set the medium-quality settings of the desktop display.
<code>RemoteDisplay.maxQualityJPE G</code>	available range of values: 1-100	90	Specifies the image quality of the desktop display for JPEG/PNG encoding. The high-quality settings are for areas of the screen that are more static, resulting in a better image quality.

**Configuration Options in `/etc/vmware/viewagent-custom.conf`**

Java Standalone Agent uses the configuration file `/etc/vmware/viewagent-custom.conf`.

**Table 6-2.** Configuration Options in `/etc/vmware/viewagent-custom.conf`

Option	Value	Default	Description
Subnet	NULL or network address and mask in IP address/CIDR format	NULL	<p>If there are multiple local IP addresses with different subnets, use this option to set the subnet that the Linux Agent provides to the View Connection Server.</p> <p>When multiple subnet configurations are detected on a Linux Agent machine, this option is required to specify the correct subnet that should be used by the Linux Agent. For example, if you installed Docker on the Linux machine, it will be introduced as a virtual network adapter. To avoid Linux Agent from using Docker as a virtual network adapter, you have to set this option to use the real physical network adapter.</p> <p>You must specify the value in IP address/CIDR format. For example, Subnet=192.168.1.0/24.</p> <p>NULL implies that the Linux Agent randomly selects the IP address.</p>
SSOEnable	true or false	true	Set this option to enable/disable single sign-on (SSO).
SSOUserFormat	A text string	[username]	<p>Use this option to specify the format of the login name for single sign-on. The default is the user name only. Set this option if the domain name is also required. Typically the login name is the domain name plus a special character followed by the user name. If the special character is the backslash, you must escape it with another backslash. Examples of login name formats:</p> <ul style="list-style-type: none"> <li>■ SSOUserFormat=[domain]\&lt;[username]</li> <li>■ SSOUserFormat=[domain]+[username]</li> <li>■ SSOUserFormat=[username]@[domain]</li> </ul>
CDREnable	true or false	true	Set this option to enable or disable the Client Drive Redirection (CDR) feature.
USBEnable	true or false	true	Set this option to enable or disable the USB Redirection feature.
KeyboardLayoutSync	true or false	true	<p>Use this option to specify whether to synchronize a client's system locale list and current keyboard layout with the Horizon Agent for Linux desktops.</p> <p>When this setting is enabled or not configured, synchronization is allowed. When this setting is disabled, synchronization is not allowed.</p> <p>This feature is supported only for Horizon Client for Windows, and only for the English, French, German, Japanese, Korean, Spanish, Simplified Chinese, and Traditional Chinese locales.</p>
StartBlastServerTimeout	An integer	20	This option determines the amount of time, in seconds, that the VMwareBlastServer process has for initialization. If the process is not ready within this timeout value, the user's login will fail.
SSLCiphers	A text string	!aNULL:kECDH+AESGCM:ECDH+AESGCM:RSA+AESGCM:kECDH+AES:ECDH+AES:RSA+AES	<p>Use this option to specify the list of ciphers. You must use the format that is defined in <a href="https://www.openssl.org/docs/manmaster/apps/ciphers.html">https://www.openssl.org/docs/manmaster/apps/ciphers.html</a>.</p>
SSLProtocols	A text string	TLSv1_1:TLSv1_2	Use this option to specify the security protocols. The supported protocols are TLSv1.0, TLSv1.1, and TLSv1.2.

**Table 6-2.** Configuration Options in `/etc/vmware/viewagent-custom.conf` (Continued)

Option	Value	Default	Description
SSLCipherServerPreference	true or false	true	Use this option to enable or disable the option <code>SSL_OP_CIPHER_SERVER_PREFERENCE</code> . For more information, see <a href="https://www.openssl.org/docs/manmaster/ssl/SSL_CTX_set_options.html">https://www.openssl.org/docs/manmaster/ssl/SSL_CTX_set_options.html</a> .
UseGnomeFlashback	true or false	false	This option determines whether to use the GNOME Flashback (Metacity) desktop environment if it is installed in an Ubuntu 14.04 or Ubuntu 16.04 system. The option takes effect regardless if the SSO feature is enabled or not.  After this option is set to <b>TRUE</b> , the GNOME Flashback (Metacity) desktop environment is always used instead of the default desktop environment.  <b>Tip</b> To improve your system's performance, configure <b>UseGnomeFlashback=TRUE</b> after you have installed the GNOME Flashback (Metacity) desktop on your Ubuntu 14.04 or Ubuntu 16.04 system.
LogCnt	An integer	-1	Use this option to set the reserved log file count in <code>/tmp/vmware-root</code> . <ul style="list-style-type: none"> <li>■ -1 - keep all</li> <li>■ 0 - delete all</li> <li>■ &gt; 0 - reserved log count.</li> </ul>
RunOnceScript			Use this option to rejoin the cloned VM to AD. Set the run once script after the host name has changed. The specified script is executed only once after the first host name change. The script is executed as root permission when the agent service starts and host name has been changed since agent installation.  For example, for the winbind solution, you must join the base VM to AD with winbind, and set this option to a script path. This must contain the domain rejoin command <code>/usr/bin/net ads join -U &lt;ADUserName&gt; %&lt;ADUserPassword&gt;</code> . After VM Clone, the operating system customization changes the host name. When the agent service starts, the script is executed to join the cloned VM to AD.
RunOnceScriptTimeout		120	Use this option to set the timeout time in seconds for the <code>RunOnceScript</code> option.  For example, set <code>RunOnceScriptTimeout=120</code>

**NOTE** The three security options, `SSLCiphers`, `SSLProtocols`, and `SSLCipherServerPreference` are for the `VMwareBlastServer` process. When starting the `VMwareBlastServer` process, the Java Standalone Agent passes these options as parameters. When Blast Secure Gateway (BSG) is enabled, these options affect the connection between BSG and the Linux desktop. When BSG is disabled, these options affect the connection between the client and the Linux desktop.

## Example Blast Settings for Linux Desktops

You can adjust the image quality of your remote desktop display to improve the user experience. Improving image quality is helpful in maintaining a consistent user experience when there is a bad network connection.

## Example VMware Blast Extreme Protocol Settings

`VMwareBlastServer` and its related plug-ins use the configuration file `/etc/vmware/config`.

**Table 6-3.** Example Blast Configuration Options in `/etc/vmware/config`

Option name	Parameter	High-speed LAN	LAN	Dedicated WAN	Broadband WAN	Low-speed WAN	Extremely Low speed
Bandwidth settings	RemoteDisplay.maxBandwidthKbps	1000000 (1 Gbps)	1000000 (1 Gbps)	1000000 (1 Gbps)	5000 (5 Mbps)	2000 (2 Mbps)	1000 (1 Mbps)
Max FPS	RemoteDisplay.maxFPS	60	30	30	20	15	5
Audio Playback	RemoteDisplay.allowAudio	TRUE	TRUE	TRUE	TRUE	TRUE	FALSE
Display Quality (JPEG/PNG)	RemoteDisplay.maxQualityJPEG	90	90	90	70	60	50
Display Quality (JPEG/PNG)	RemoteDisplay.midQualityJPEG	35	35	35	35	35	35
Display Quality (JPEG/PNG)	RemoteDisplay.minQualityJPEG	25	25	25	20	20	20
Display Quality (H.264)	RemoteDisplay.qpmaxH264	28	36	36	36	36	42
Display Quality (H.264)	RemoteDisplay.qpminH264	10	10	10	10	10	10

## Examples of Client Drive Redirection Options for Linux Desktops

Configure client drive redirection (CDR) options to determine whether a local system's shared folders and drives can be accessed from the remote Linux desktops.

Configure CDR settings by adding entries to the `/etc/vmware/config` file.

The following configuration example shares the `d:\ebooks` and `C:\spreadsheets` folders, makes both folders read-only, and prevents the client from sharing more folders.

```
cdserver.forcedByAdmin=true
cdserver.sharedFolders=d:\ebooks,;c:\spreadsheets,
cdserver.permissions=R
```

In the previous example, the comma `,` placed after `ebooks` and `spreadsheets` is mandatory for correct option parsing.

Any `"R"` included in the `cdserver.sharedFolders` option would impact all the folders listed in that setting. In the following example, the `ebooks` and `spreadsheets` folders are both read-only even if the `R` value is only placed after `/home/jsmith` folder path.

```
cdserver.sharedFolders=d:\ebooks,;c:\spreadsheets,;/home/jsmith,R
```

## Suppress the vSphere Console Display of a Linux Desktop

When a user connects to a Linux desktop, the desktop can also be displayed in the vSphere console for the Linux virtual machine. You can configure Linux virtual machines to ensure that the vSphere console is blank when users connect to their desktops.

### Procedure

- ◆ On the ESXi host, add the following line to the Linux virtual machine's `vmx` file.

```
RemoteDisplay.maxConnections = "0"
```

The vSphere console display remains blank even when you connect to the virtual machine when the user is logged out of the desktop.





# Create and Manage Linux Desktop Pools

# 7

To configure Linux virtual machines for use as remote desktops, you must create a desktop pool with Linux virtual machines.

Horizon for Linux supports the following desktop pool types:

- Manual desktop pool with vCenter virtual machine
- Automated full-clone desktop pool

To create a manual desktop pool with a vCenter virtual machine, you must install the Horizon agent on all virtual machines. Then, use the Connection Server desktop pool creation wizard to add the virtual machines to the desktop pool. To clone a large number of virtual machines, see [“Overview of Bulk Deployment of Linux Desktops,”](#) on page 65.

To create an automated full-clone desktop pool, you must install the Horizon agent on a Linux virtual machine template. Then, use the Connection Server desktop pool creation wizard to clone full virtual machines.

This chapter includes the following topics:

- [“Create a Manual Desktop Pool for Linux,”](#) on page 57
- [“Manage Desktop Pool for Linux,”](#) on page 58
- [“Create an Automated Full-Clone Desktop Pool for Linux,”](#) on page 59
- [“Broker PowerCLI Commands,”](#) on page 61

## Create a Manual Desktop Pool for Linux

You can create a manual desktop pool for Linux virtual machines.

### Prerequisites

- Verify that Horizon Agent is installed on the Linux guest operating systems. See [“Install Horizon Agent on a Linux Virtual Machine,”](#) on page 41.
- Verify that vCenter Server is added to Horizon Connection Server.

### Procedure

- 1 In View Administrator, add a manual desktop pool.  
Select **Catalog > Desktop Pools > Add** .
- 2 Select **Manual Desktop Pool**.
- 3 On the User assignment page, select either dedicated or floating user assignments for the machines in the desktop pool and click **Next**.

- 4 On the Machine Source page, select **vCenter virtual machines** and click **Next**.
- 5 On the vCenter Server page, select the appropriate vCenter server and click **Next**.
- 6 Enter the **desktop pool id**.
- 7 On the Desktop Pool Settings page, set the following options.

Option	Description
<b>Default display protocol</b>	VMware Blast
<b>Allow users to choose protocol</b>	No
<b>3D Renderer</b>	Manage using vSphere Client for 2D, vSGA, or vDGA desktop and NVIDIA GRID vGPU for vGPU desktop

**NOTE** The pool settings are mandatory. Else, you might fail to connect to the desktop and get a protocol error or a black screen.

- 8 On the Add vCenter Virtual Machines page, select the linux virtual machine. Click **Add** and click **Next**.

**NOTE** Do not create Windows and Linux virtual machines in the same desktop pool.

- 9 Follow the prompts to complete the procedure.

Entitle users to the machines in the desktop pool. In View Administrator, select the desktop pool, select **Entitlements > Add entitlement**, and add users or groups.

The Linux virtual machines are ready to be used as remote desktops in a Horizon 7 deployment.

## Manage Desktop Pool for Linux

When you create a manual desktop pool and add Linux machines to the pool, you can manage the manual desktop pools by configuring the settings. You must add only Linux guest operating systems to the manual desktop pool. If the pool contains both Windows and Linux guest operating systems, the pool is treated as a Windows pool, and you will be unable to connect to the Linux desktops.

### Support for Managing Operations

- Disable or Enable desktop pool
- Clone automated desktop pool
- Delete desktop pool

You can either remove virtual machines from View Manager or delete virtual machines from the disk

### Support for Remote Settings

**Table 7-1.** Remote Settings

Remote Setting	Options
Remote Machine Power Policy	<ul style="list-style-type: none"> <li>■ Take no power action</li> <li>■ Ensure machines are always powered on</li> <li>■ Suspend</li> <li>■ Power off</li> </ul>
Automatically logoff after disconnect	<ul style="list-style-type: none"> <li>■ Immediately</li> <li>■ Never</li> <li>■ After n minutes</li> </ul>

**Table 7-1.** Remote Settings (Continued)

Remote Setting	Options
Allow users to reset/restart their machines	<ul style="list-style-type: none"> <li>■ Yes</li> <li>■ No</li> </ul>
Allow user to initiate separate sessions from different client devices	<ul style="list-style-type: none"> <li>■ Yes</li> <li>■ No</li> </ul>
"Delete machine after logoff" for Automated Desktop Pool with Full Clone and Floating	<ul style="list-style-type: none"> <li>■ Yes</li> <li>■ No</li> </ul>

## Support for View Administrator Operations

- Disconnect Session
- Logoff Session
- Reset/Restart Desktop
- Send Message

For dedicated desktop pool, you can add or remove user assignment for each virtual machine. For large number of operations, you must use View PowerCLI Cmdlets.

- Update-UserOwnership
- Remove-UserOwnership

**NOTE** Do not change **Remote Display Protocol** settings. This setting must always be the same as desktop pool creation.

Setting	Option
Default display protocol	VMware Blast
Allow user to choose protocol	No
3D Renderer	<ul style="list-style-type: none"> <li>■ Manage using vSphere Client for 2D or vSGA or vDGA</li> <li>■ NVIDIA GRID vGPU</li> </ul>

For more information, see *View Administration* guide.

## Create an Automated Full-Clone Desktop Pool for Linux

You can create an automated full-clone desktop pool for Linux virtual machines. After you create the automated full-clone desktop pool, you can use the Linux virtual machines as remote desktops in a Horizon 7 deployment.

### Prerequisites

- Verify that Horizon Agent is installed on the Linux guest operating systems. See [“Install Horizon Agent on a Linux Virtual Machine,”](#) on page 41.
- If you use the Winbind solution to join the Linux virtual machine to Active Directory, you must finish configuring the Winbind solution in the virtual machine template.
- If you use the Winbind solution, you must run the domain join command on the virtual machine. Include the command in a shell script and specify the script path to the Horizon Agent option RunOnceScript in `/etc/vmware/viewagent-custom.conf`. For more information, see [“Setting Options in Configuration Files on a Linux Desktop,”](#) on page 47.
- Verify that vCenter Server is added to Horizon Connection Server.

**Procedure**

- 1 Create a guest customization specification.

See "Create a Customization Specification for Linux in the vSphere Web Client" in the *vSphere Virtual Machine Administration* document. When you create the specification, make sure that you specify the following settings correctly.

Setting	Value
Target Virtual Machine OS	Linux
Computer Name	Use the virtual machine name.
Domain	Specify the domain of the View environment.
Network Settings	Use standard network settings.
Primary DNS	Specify a valid address.

**NOTE** For more information on Guest OS Customization Support Matrix, see <http://partnerweb.vmware.com/programs/guestOS/guest-os-customization-matrix.pdf>.

- 2 In Horizon Administrator, select **Catalog > Desktop Pools > Add**.
- 3 Select **Automated Desktop Pool** and click **Next**.
- 4 Select either dedicated or floating user assignments for the machines in the desktop pool and click **Next**.
- 5 On the vCenter Server page, select **Full virtual machines** and select the appropriate vCenter server, and click **Next**.
- 6 On the Desktop Pool Identification page, enter the desktop pool ID and click **Next**.
- 7 On the Desktop Pool Settings page, set the following options and click **Next**.

Option	Description
<b>Default display protocol</b>	VMware Blast
<b>Allow users to choose protocol</b>	No
<b>3D Renderer</b>	Manage using vSphere Client for 2D, vSGA, or vDGA desktop and NVIDIA GRID vGPU for vGPU desktop

**NOTE** The pool settings are mandatory. Else, you might fail to connect to the desktop and get a protocol error or a black screen.

- 8 On the Provisioning Settings page, set the **Virtual Machine Naming** options and click **Next**.

Option	Description
<b>Specify names manually</b>	Enter names manually.
<b>Use a naming pattern</b>	For example, specify <code>LinuxVM-{n}</code> . You must also specify the following desktop pool sizing options: <ul style="list-style-type: none"> <li>■ Maximum number of machines</li> <li>■ Number of spare, powered-on machines</li> </ul>

- 9 On the Storage Optimization page, select a storage management policy and click **Next**.
- 10 On the vCenter Settings page, you must click Browse and select the vCenter Server settings in sequence and click **Next**.

You cannot skip a vCenter Server setting:

- a Template

- b VM folder location
  - c Host or cluster
  - d Resource pool
  - e Datastores
- 11 On the Advanced Storage Options page, select the appropriate storage options and click **Next**.
  - 12 On the Guest Customization page, select your guest customization for Linux and click **Next**.
  - 13 On the Ready to Complete page, review the details and select **Entitle users after this wizard finishes**.
  - 14 Click **Finish**.
  - 15 To entitle users to the machines in the desktop pool, select the desktop pool and click **Entitlements > Add entitlements** and add the users and groups.
  - 16 Wait till all the Linux virtual machines in the desktop pool become available.

## Broker PowerCLI Commands

The View PowerCLI cmdlets which are to perform various administration tasks on Connection Server and Windows desktop, can also work for Linux desktop.

### Create a Manual Desktop Pool

```
Add-ManualPool -DefaultProtocol Blast -AllowProtocolOverride $false -threadRender usevc|vgpu -
Pool_id <pool id> [more parameters]
```

For Linux Desktop the following options and values are mandatory.

- DefaultProtocol Blast
- AllowProtocolOverride \$false
- threadRender usevc|vgpu. For vGPU desktop, use -threadRender vgpu and for 2D/vSGA/vDGA desktop -threadRender usevc .

#### Examples

- Create a floating Linux Desktop pool named LinuxDesktop with a virtual machine, LinuxVM-01.
 

```
Add-ManualPool -DefaultProtocol Blast -AllowProtocolOverride $false -threadRender usevc -
Pool_id LinuxDesktop -Id (Get-DesktopVM -Name LinuxVM-01).id -Persistence NonPersistent -
Vc_name myvc.myorg.org
```
- Create a dedicated Linux vGPU desktop pool named LinuxDesktop with all VMs that start with VM name as LinuxVM-.
 

```
Get-DesktopVM | Where-Object {$_.Name.StartsWith("LinuxVM-")} | Add-ManualPool -
DefaultProtocol Blast -AllowProtocolOverride $false -Persistence Persistent -threadRender
vgpu -Pool_id LinuxDesktop
```
- Create floating Linux desktop pool LinuxDesktop with the first RHEL 6 x64 VM.
 

```
Get-DesktopVM | Where-Object {$_.GuestID -eq "rhel6_64Guest"} | Select-Object -Index 0 |
Add-ManualPool -DefaultProtocol Blast -AllowProtocolOverride $false -Persistence
NonPersistent -threadRender usevc -Pool_id LinuxDesktop
```

## Create a Full-Clone Automated Desktop Pool

```
Add-AutomaticPool -DefaultProtocol Blast -AllowProtocolOverride $false -threadRender usevc|vgpu `
-Pool_id <pool id> -Vc_id <vCenter id> `
-NamePrefix <VM Name Prefix> `
-templatePath <Virtual Machine Template Path> `
-VmFolderPath <Virtual Machine Folder Path> `
-ResourcePoolPath <Resource Pool Path> `
-dataStorePaths <Datastore Path> `
-customizationSpecName <Customization Specification Name> `
[more parameters]
```

For Linux Desktop the following options and values are mandatory.

- DefaultProtocol Blast
- AllowProtocolOverride \$false
- threadRender usevc|vgpu. For vGPU desktop, use -threadRender vgpu and for 2D/vSGA desktop -threadRender usevc.

### Example

```
Add-AutomaticPool -DefaultProtocol Blast -AllowProtocolOverride $false -threadRender usevc `
-pool_id FullClone-Linux `
-Vc_id (Get-ViewVC -serverName myvc.myorg.org).vc_id `
-NamePrefix "FullClone-{n:fixed=3}" `
-Persistence NonPersistent -deletePolicy DeleteOnUse `
-VmFolderPath "/LinuxVDI/vm/FullClone" `
-ResourcePoolPath "/LinuxVDI/host/LinuxVDICluster/Resources" `
-templatePath "/LinuxVDI/vm/LinuxTemplate" `
-dataStorePaths "/LinuxVDI/host/LinuxVDICluster/datastore" `
-customizationSpecName "linux-spec" `
-maximumCount 100
```

## Add or Remove Desktop Pool Entitlement

- Entitle domain user group of domain mydomain.org to LinuxDesktop.

```
Add-PoolEntitlement -Pool_id LinuxDesktop -Sid (Get-User -Name "domain user" -Domain
"mydomain.org").sid
```

- Remove entitlement of domain user group of mydomain.org domain from LinuxDesktop.

```
Remove-PoolEntitlement -Pool_id LinuxDesktop -Sid (Get-User -Name "domain user" -Domain
"mydomain.org").sid
```

## Assign or Remove User To or From the VM in Dedicated Desktop Pool

- Assign myuser user to LinuxVM-01 VM which is in a dedicated desktop pool.

```
Update-UserOwnership -Machine_id (Get-DesktopVM -Name "LinuxVM-01").machine_id -Sid (Get-
User -Name "myuser" | Where-Object {$_.cn -eq "myuser"}).sid
```

- Remove myuser user from LinuxVM-01 VM which is in a dedicated desktop pool.

```
Remove-UserOwnership -Machine_id (Get-DesktopVM -Name "LinuxVM-01").machine_id
```

## Logoff Desktop Connection

- Logoff from the desktop session of myuser.

```
Get-RemoteSession -Username "mydomain.org\myuser" | Send-SessionLogoff
```

For more information on broker PowerCLI cmdlet, see Using View PowerCLI in *View Integration*.





# Bulk Deployment of Horizon 7 for Manual Desktop Pools

---

# 8

With View Administrator, you can create a pool of Windows, but not Linux, desktop machines automatically. However, you can develop scripts that automate the deployment of a pool of Linux desktop machines.

The sample scripts that are provided are for illustration purposes only. VMware does not accept any responsibility for issues that might arise when you use the sample scripts.

This chapter includes the following topics:

- [“Overview of Bulk Deployment of Linux Desktops,”](#) on page 65
- [“Overview of Bulk Upgrade of Linux Desktops,”](#) on page 67
- [“Create a Virtual Machine Template for Cloning Linux Desktop Machines,”](#) on page 67
- [“Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops,”](#) on page 69
- [“Sample Script to Clone Linux Virtual Machines,”](#) on page 69
- [“Sample Script to Join Cloned Virtual Machines to AD Domain,”](#) on page 73
- [“Sample Script to Join Cloned Virtual Machines to AD Domain Using SSH,”](#) on page 76
- [“Sample Script to Upload Configuration Files to Linux Virtual Machines,”](#) on page 79
- [“Sample Script to Upload Configuration Files to Linux Virtual Machines Using SSH,”](#) on page 83
- [“Sample Script to Upgrade Horizon Agent on Linux Desktop Machines,”](#) on page 87
- [“Sample Script to Upgrade Horizon Agent on Linux Virtual Machines Using SSH,”](#) on page 91
- [“Sample Script to Perform Operations on Linux Virtual Machines,”](#) on page 97

## Overview of Bulk Deployment of Linux Desktops

Deploying manual desktops for Linux involve several steps. If you plan to deploy more than a few desktops, you can automate some of the steps by using PowerCLI scripts.

For some operations, you can choose to have either PowerCLI or SSH execute the commands on the Linux machine. The following table describes the differences between the two approaches.

PowerCLI	SSH
No need to install additional tools.	<ul style="list-style-type: none"> <li>■ For Ubuntu, you need to install the SSH server with the command <code>sudo apt-get install openssh-server</code>. For RHEL and CentOS, openssh-server is installed by default but you need to ensure that the firewall settings allow ssh.</li> <li>■ Need to download the SSH client applications <code>pscp.exe</code> and <code>plink.exe</code> and put them in the same folder as the PowerCLI scripts.</li> </ul>
Uploading files and command execution are slower.	Uploading files and command execution are faster.
Need to supply the ESXi host's administrator credentials.	No need to supply the ESXi host's administrator credentials.
Cannot handle special characters in the administrator's password when running the script to install Horizon Agent or the AD user's password when running the script to join the domain.	Can handle special characters in the administrator's password when running the script to install Horizon Agent or the AD user's password when running the script to join the domain.

**NOTE** Both PowerCLI-based and SSH-based scripts can handle special characters in the passwords for the vCenter Server administrator and the Linux administrator. PowerCLI-based scripts can also handle special characters in the ESXi host administrator's password. In all these cases, an escape character is not necessary.

For more information about vSphere PowerCLI, see <https://www.vmware.com/support/developer/PowerCLI>.

The process of bulk deploying a pool of Linux desktops involves the following steps:

- 1 Create a virtual machine template and install Horizon Agent on the virtual machine.  
See [“Create a Virtual Machine Template for Cloning Linux Desktop Machines,”](#) on page 67.
- 2 Create a guest customization specification.  
See "Create a Customization Specification for Linux in the vSphere Web Client" in the *vSphere Virtual Machine Administration* document. When you create the specification, make sure that you specify the following settings correctly.

Setting	Value
Target Virtual Machine OS	Linux
Computer Name	Use the virtual machine name.
Domain	Specify the domain of the View environment.
Network Settings	Use standard network settings.
Primary DNS	Specify a valid address.

**NOTE** For more information on Guest OS Customization Support Matrix, see <http://partnerweb.vmware.com/programs/guestOS/guest-os-customization-matrix.pdf>.

- 3 Clone virtual machines.  
See [“Sample Script to Clone Linux Virtual Machines,”](#) on page 69.
- 4 Join the cloned VMs to the Active Directory (AD) domain if you are using the winbind solution. You can run the domain join command with example scripts below or use option `RunOnceScript` in `/etc/vmware/viewagent-custom.conf`, configured in the template virtual machine.  
See [“Sample Script to Join Cloned Virtual Machines to AD Domain,”](#) on page 73 or [“Sample Script to Join Cloned Virtual Machines to AD Domain Using SSH,”](#) on page 76.
- 5 Update configuration options in virtual machines.

See [“Sample Script to Upload Configuration Files to Linux Virtual Machines,”](#) on page 79 or [“Sample Script to Upload Configuration Files to Linux Virtual Machines Using SSH,”](#) on page 83.

- 6 Create a desktop pool.

See [“Create a Manual Desktop Pool for Linux,”](#) on page 57.

For a sample script that performs operations such as powering on, shutting down, restarting, or deleting virtual machines, see [“Sample Script to Perform Operations on Linux Virtual Machines,”](#) on page 97. This script can delete virtual machines from vCenter Server.

## Overview of Bulk Upgrade of Linux Desktops

Bulk upgrade of manual desktops for Linux involve several steps. You can automate some of the steps by using PowerCLI scripts.

### Bulk Upgrade Unmanaged Desktop

To bulk upgrade the unmanaged virtual machine to managed or unmanaged virtual machine, you must use the sample upgrade script to upload the new Horizon Agent to the existing virtual machines and run upgrade command.

- If you retain the unmanaged virtual machine, your existing desktop pool can be reused.
- If you upgrade from unmanaged virtual machine to managed virtual machine, you must delete the existing desktop pool and create a new desktop pool. For more information, see [“Upgrade Horizon Agent on a Linux Virtual Machine,”](#) on page 45.

### Bulk Upgrade Managed Desktop

To bulk upgrade the managed virtual machine, select one of the following methods.

Method	Description
In the template virtual machine, install or upgrade the new Horizon Agent and create a snapshot.	<ul style="list-style-type: none"> <li>■ The user data and profile are lost since the existing virtual machines are deleted, unless the user data and profile are located on the share server such as NFS server.</li> <li>■ After the virtual machine replacement, the state of the virtual machine on View Administrator might be missing. You must restart the broker service to fix it.</li> <li>■ If you are using linked clone, this method avoids duplicate data on each virtual machine.</li> </ul>
Use the sample script of upgrade to upload the new Horizon Agent to existing virtual machines and run the upgrade command.	<ul style="list-style-type: none"> <li>■ User data and profile is retained.</li> <li>■ If you are using linked clone, this method introduces duplicate data on each virtual machine.</li> </ul>

## Create a Virtual Machine Template for Cloning Linux Desktop Machines

Before you perform virtual machine cloning, you must create a virtual machine template that the clones are based on.

### Prerequisites

- Verify that your deployment meets the requirements for supporting Linux desktops. See [“System Requirements for Horizon 7 for Linux,”](#) on page 11.

- Familiarize yourself with the steps for creating virtual machines in vCenter Server and installing guest operating systems. See "Creating and Preparing Virtual Machines" in the *Setting Up Virtual Desktops in Horizon 7* document.
- Familiarize yourself with the recommended video memory (vRAM) values for the monitors you will use with the virtual machine. See "[System Requirements for Horizon 7 for Linux](#)," on page 11.
- Familiarize yourself with the steps for AD integration. See [Chapter 3, "Setting Up Active Directory Integration for Linux Desktops,"](#) on page 25.
- Familiarize yourself with the steps to install Horizon Agent on Linux. See Chapter "Installing Horizon Agent and Managing Linux Desktops"
- If required, familiarize yourself with the steps to configure options using the View configuration files. See [Chapter 6, "Configuration Options for Linux Desktops,"](#) on page 47.
- If you plan to set up graphics, familiarize yourself with the steps. See [Chapter 4, "Setting Up Graphics for Linux Desktops,"](#) on page 29.

### Procedure

- 1 In vSphere Web Client or vSphere Client, create a new virtual machine.
- 2 Configure custom configuration options.
  - a Right-click the virtual machine and click **Edit Settings**.
  - b Specify the number of vCPUs and the vMemory size.
 

For recommended values, follow the guidelines in the installation guide for your Linux distribution.

For example, Ubuntu 12.04 recommends configuring 2048 MB for vMemory and 2 vCPUs.
  - c Select **Video card** and specify the number of displays and the total video memory (vRAM).
 

Set the vRAM size in vSphere Web Client for virtual machines that use 2D or vSGA, which use the VMware driver. The vRAM size has no affect on vDGA or NVIDIA GRID vGPU machines, which use NVIDIA drivers.

For recommended values, follow the guidelines in *System Requirements for Horizon 7 for Linux*. Do not use the Video Memory Calculator.
- 3 Power on the virtual machine and install the Linux distribution.
- 4 Create a user with root privileges, for example, ViewUser. This user is used to install and uninstall Horizon Agent only.
- 5 Edit `/etc/sudoers` and add the line `ViewUser ALL=(ALL) NOPASSWD:ALL`.
 

With this line in `/etc/sudoers`, no password is required to run `sudo` as ViewUser. When you run the sample script to install Horizon Agent that is provided in this chapter, you specify ViewUser as an input.
- 6 If the Linux distribution is RHEL, CentOS, or NeoKylin, edit `/etc/sudoers` and comment out the following lines:
 

```
Defaults requiretty
Defaults !visiblepw
```
- 7 If the Linux distribution is not RHEL 7, CentOS 7, SLED 12, or SLES 12, install VMware Tools .
 

RHEL 7, CentOS 7, SLED 12, and SLES 12 have Open VM Tools installed by default.
- 8 If the Linux distribution is RHEL 7, CentOS 7, or SLES 12, install the `deployPkg` plug-in.
 

The instructions are at <http://kb.vmware.com/kb/2075048>.

- 9 For RHEL and CentOS, enable the Network Connection setting **Connect automatically**.
- 10 Perform the AD integration tasks.
- 11 Perform the steps to set up graphics.
- 12 Install Horizon agent
 

```
sudo ./install_viewagent.sh -A yes
```
- 13 Perform additional configurations using the View configuration files.
- 14 Shut down the virtual machine and create a snapshot.

## Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops

The sample PowerCLI scripts to deploy Linux desktops read one input file that contains information about the desktop machines.

The input file is of type csv and contains the following information:

- Desktop virtual machine name
- Parent virtual machine name
- Guest customization specification
- Datastore where the cloned desktop machine resides
- ESXi server that hosts the desktop machine
- Parent virtual machine's snapshot that is used for cloning
- Flag that indicates whether to delete the desktop virtual machine if it exists

The following example shows what the input file may contain.

```
VMName,Parentvm,CustomSpec,Datastore,Host,FromSnapshot,DeleteIfPresent
linux-001,Ubuntu1204x64,linuxagent,datastore1,10.117.44.172,snapshot1,TRUE
linux-002,Ubuntu1204x64,linuxagent,datastore1,10.117.44.172,snapshot1,TRUE
linux-003,Ubuntu1204x64,linuxagent,datastore1,10.117.44.172,snapshot1,TRUE
linux-004,Ubuntu1204x64,linuxagent,datastore1,10.117.44.172,snapshot1,TRUE
linux-005,Ubuntu1204x64,linuxagent,datastore1,10.117.44.172,snapshot1,TRUE
```

The sample scripts assume that the name of this input file is `CloneVMs.csv` and that the file is located in the same folder as the scripts.

## Sample Script to Clone Linux Virtual Machines

You can customize and use the following sample script to clone any number of virtual machines (VMs).

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at [https://www.vmware.com/support/pubs/view\\_pubs.html](https://www.vmware.com/support/pubs/view_pubs.html).

### Script Input

This script reads one input file, which is described in “[Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#),” on page 69. This script also interactively asks for the following information:

- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- Clone type, which can be linked or full

- Whether to disable vSphere VM console

## Script Content

```
<#
Create Clones from a Master VM

The Tool supports creation of Full clone and linked clone from Master VM.
The parent VM is required for the linked-clone to work and the parent VMs file cannot be renamed
or moved.
#>
#----- Functions -----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}

function IsVMExists ()
{
    Param($VMExists)
    Write-Host "Checking if the VM $VMExists already Exists"
    [bool]$Exists = $false

    #Get all VMS and check if the VMS is already present in VC
    $listvm = Get-vm
    foreach ($lvm in $listvm)
    {
        if($VMExists -eq $lvm.Name )
        {
            $Exists = $true
        }
    }
    return $Exists
}

function Disable_VM_Console()
{
    Param($VMToDisableConsole)
    $svmConfigSpec = New-Object VMware.Vim.VirtualMachineConfigSpec
```

```

    $extra = New-Object VMware.Vim.optionvalue
    $extra.Key="RemoteDisplay.maxConnections"
    $extra.Value="0"
    $vmConfigSpec.extraconfig += $extra
    $vm = Get-VM $VMToDisableConsole | Get-View
    $vm.ReconfigVM($vmConfigSpec)
}

function Delete_VM()
{
    Param($VMToDelete)
    Write-Host "Deleting VM $VMToDelete"
    Get-VM $VMToDelete | where { $_.PowerState -eq "PoweredOn" } | Stop-VM -confirm:$false
    Get-VM $VMToDelete | Remove-VM -DeleteFromDisk -confirm:$false
}

#----- Main Script -----

$vcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$vcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$vcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
$cloneType = GetInput -prompt 'Clone Type ("linked" or "full")' -IsPassword $false
$disableVMConsole = GetInput -prompt 'Disable vSphere VM Console ("yes" or "no", recommend
"yes")' -IsPassword $false
"-----"
$csvFile = '.\CloneVMs.csv'

# Check that user passed only linked or full clone
if (($cloneType.length >0) -and ($cloneType -ne "linked" -or $cloneType -ne "full"))
{
    write-host -ForegroundColor Red "Clone type supports only 'linked' or 'full' (case
sensitive)"
    exit
}
if (($disableVMConsole.length >0) -and ($disableVMConsole -ne "yes" -or $disableVMConsole -ne
"no"))
{
    write-host -ForegroundColor Red "Disable vSphere VM Console supports only 'yes' or 'no'
(case sensitive)"
    exit
}

#check if file exists
if (!(Test-Path $csvFile))
{
    write-host -ForegroundColor Red "CSV File $CSVFile not found"
    exit
}

# Connect to the VC (Parameterize VC)
#Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))
{

```

```

    Write-Host 'Exit since failed to login vCenter'
    exit
}
else
{
    Write-Host 'vCenter is connected'
}

#Read input CSV file
$csvData = Import-CSV $csvFile
#$csvData = Import-CSV $csvFile -
header("VMName","Parentvm","CustomSpec","Datastore","Host","FromSnapshot","DeleteIfPresent")
foreach ($line in $csvData)
{
    "`n-----"
    $VMName = $line.VMName
    write-host -ForegroundColor Yellow "VM: $VMName`n"

    $destVMName=$line.VMName
    $srcVM = $line.Parentvm
    $cSpec = $line.CustomSpec
    $targetDSName = $line.Datastore
    $destHost = $line.Host
    $srcSnapshot = $line.FromSnapshot
    $deleteExisting = $line.DeleteIfPresent
    if (IsVMExists ($destVMName))
    {
        Write-Host "VM $destVMName Already Exists in VC $vcAddress"
        if($deleteExisting -eq "TRUE")
        {
            Delete_VM ($destVMName)
        }
        else
        {
            Write-Host "Skip clone for $destVMName"
            continue
        }
    }
    $vm = get-vm $srcvm -ErrorAction Stop | get-view -ErrorAction Stop
    $cloneSpec = new-object VMware.VIM.VirtualMachineCloneSpec
    $cloneSpec.Location = new-object VMware.VIM.VirtualMachineRelocateSpec
    if ($CloneType -eq "linked")
    {
        $cloneSpec.Location.DiskMoveType =
[VMware.VIM.VirtualMachineRelocateDiskMoveOptions]::createNewChildDiskBacking
    }
    Write-Host "Using Datastore $targetDSName"
    $newDS = Get-Datastore $targetDSName | Get-View
    $CloneSpec.Location.Datastore = $newDS.summary.Datastore
    Set-VM -vm $srcVM -snapshot (Get-Snapshot -vm $srcVM -Name $srcSnapshot) -confirm:$false
    $cloneSpec.Snapshot = $vm.Snapshot.CurrentSnapshot
    $cloneSpec.Location.Host = (get-vmhost -Name $destHost).Extensiondata.MoRef
    $cloneSpec.Location.Pool = (Get-ResourcePool -Name Resources -Location (Get-VMHost -Name
$destHost)).Extensiondata.MoRef
    # Start the Clone task using the above parameters

```



```

$task = $vm.CloneVM_Task($vm.parent, $destVMName, $cloneSpec)
# Get the task object
$task = Get-Task | where { $_.id -eq $task }
#Wait for the taks to Complete
Wait-Task -Task $task

$newvm = Get-vm $destVMName
$customSpec = Get-OSCustomizationSpec $cSpec
Set-vm -OSCustomizationSpec $cSpec -vm $newvm -confirm:$false
if ($disableVMConsole -eq "yes")
{
    Disable_VM_Console($destVMName)
}
# Start the VM
Start-VM $newvm
}
Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

## Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\CloneVMs.ps1
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
Clone Type<"linked" or "Full"> : linked
Disable vSphere VM Console ("yes" or "no", recommend "yes") : yes

```

The time that the cloning process takes depends on the number of desktop machines and can range from several minutes to a number of hours. To verify that the process is complete, from vSphere client, make sure that the last desktop virtual machine is powered on, has its own unique host name, and VMware Tools is running.

## Sample Script to Join Cloned Virtual Machines to AD Domain

You can customize and use the following sample script to join cloned virtual machines (VMs) to an Active Directory (AD) domain.

You need to run this script if you use the Winbind solution for AD integration because the step to join the domain will fail for the cloned VMs. This script runs a command to join the domain on each VM. You do not need to run this script if you use the OpenLDAP solution.

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at [https://www.vmware.com/support/pubs/view\\_pubs.html](https://www.vmware.com/support/pubs/view_pubs.html).

## Script Input

This script reads one input file, which is described in [“Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops,”](#) on page 69. This script also interactively asks for the following information:

- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- Administrator login name for the ESXi host

- Administrator password for the ESXi host
- User login name for the Linux VM
- User password for the Linux VM
- Login name of an AD user that is authorized to join machines to the domain
- Password of the authorized AD user

## Script Content

```
<#
.SYNOPSIS
run command "sudo /usr/bin/net ads join"

.DESCRPTION
The tool is to run the command "sudo /usr/bin/net ads join" to join Linux to AD

.NOTES
#>
#----- Functions -----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}
#----- Handle input -----
"-----"
$svcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$svcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$svcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$hostAdmin = GetInput -prompt 'Your ESXi host admin user name, such as root' -IsPassword $false
$hostPassword = GetInput -prompt "Your ESXi admin user password" -IsPassword $true
"-----"
$guestUser = GetInput -prompt 'Your VM guest OS user name' -IsPassword $false
$guestPassword = GetInput -prompt 'Your VM guest OS user password' -IsPassword $true
"-----"
$sadUser = GetInput -prompt 'Type the AD user name to join the AD' -IsPassword $false
""
```

```

``nPlease type the AD user password."
"Plase note that special character in password may not work with the script"
$adUserPassword = GetInput -prompt 'Your AD user password' -IsPassword $true
"-----"

#$csvFile = Read-Host 'Csv File '
$csvFile = '.\CloneVMs.csv'

#----- Main Script -----

#Connect to vCenter
#Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))
{
    Write-Host 'Exit since failed to login vCenter'
    exit
}
else
{
    Write-Host 'vCenter is connected'
}

#Read input CSV file
$csvData = Import-CSV $csvFile

$destFolder = "/home/$guestUser/"

#Handle VMs one by one
foreach ($line in $csvData)
{
    ``n-----"
    $VMName = $line.VMName
    write-host -ForegroundColor Yellow "VM: $VMName`n"

    $cmd = "sudo /usr/bin/net ads join -U $adUser%$adUserPassword"
    Write-Host "Run cmd 'sudo /usr/bin/net ads join' in VM '$VMName' with user '$guestUser'"
    Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
    $guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd
}

Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

## Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\ClonedVMs_JoinDomain.ps1
-----
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
-----
Your ESXi host admin user name, such as root: root
Your ESXi host admin user password: *****

```

```

-----
Your VM guest OS user name: ViewUser
Your VM guest OS user password: *****
-----
Type the AD user name to join the AD: viewadmin
Please type the AD user password.
Please note that special character in password may not work with the script.
Your AD user password: *****

```

## Sample Script to Join Cloned Virtual Machines to AD Domain Using SSH

You can customize and use the following sample script to join cloned virtual machines (VMs) to an Active Directory (AD) domain. This script uses SSH to run commands on the Linux VMs.

You need to run this script if you use the Winbind solution for AD integration because the step to join the domain will fail for the cloned VMs. This script runs a command to join the domain on each VM. You do not need to run this script if you use the OpenLDAP solution.

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at [https://www.vmware.com/support/pubs/view\\_pubs.html](https://www.vmware.com/support/pubs/view_pubs.html).

### Script Input

This script reads one input file, which is described in [“Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops,”](#) on page 69. This script also interactively asks for the following information:

- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- User login name for the Linux VM
- User password for the Linux VM
- Login name of an AD user that is authorized to join machines to the domain
- Password of the authorized AD user

### Script Content

```

<#
.SYNOPSIS
run command "sudo /usr/bin/net ads join" via SSH

.DESRIPTION
The tool is to run the command "sudo /usr/bin/net ads join" to join Linux machine to AD via SSH

.NOTES
#>
#----- Functions -----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)

```

```

    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}

function Check_SSH_Client
{
    Param($IsPlink, $IsPSCP)
    if ($IsPlink)
    {
        if (Test-Path ".\plink.exe")
        {
            write-host -ForegroundColor Yellow 'SSH client "plink.exe" found'
        }
        else
        {
            write-host -ForegroundColor Red 'SSH client "plink.exe" not found, please download
from its official web site'
            exit
        }
    }
    if ($IsPSCP)
    {
        if (Test-Path ".\pscp.exe")
        {
            write-host -ForegroundColor Yellow 'SSH client "pscp.exe" found'
        }
        else
        {
            write-host -ForegroundColor Red 'SSH client "pscp.exe" not found, please download
from its official web site'
            exit
        }
    }
}

function RunCmdViaSSH
{
    Param($VM_Name, $User, $Password, $Cmd, $returnOutput = $false)

    $VM= Get-VM $VM_Name
    $IP = $VM.guest.IPAddress[0]
    write-host "Run cmd on $VM_Name ($IP)"
    if($returnOutput)
    {

```

```

        $command = "echo yes | .\plink.exe -ssh -l $user -pw $password $IP " + "'" + $cmd + "'"
        $output = Invoke-Expression $command
        return $output
    }
    else
    {
        echo yes | .\plink.exe -ssh -l $user -pw $password $IP "$cmd"
    }
}

function UploadFileViaSSH
{
    Param($VM_Name, $User, $Password, $LocalPath, $DestPath)

    $VM= Get-VM $VM_Name
    $IP = $VM.guest.IPAddress[0]
    $command = "echo yes | .\pscp.exe -l $User -pw $Password $LocalPath $IP" + ":" + "$DestPath"
    write-host "Upload file: $command"
    Invoke-Expression $command
}

#----- Handle input -----
"-----"
Check_SSH_Client -IsPlink $true -IsPSCP $false
"-----"
$vcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$vcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$vcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$guestUser = GetInput -prompt 'Your VM guest OS user name' -IsPassword $false
$guestPassword = GetInput -prompt 'Your VM guest OS user password' -IsPassword $true
"-----"
$adUser = GetInput -prompt 'Type the AD user name to join the AD' -IsPassword $false
""
"
Please type the AD user password."
[Console]::ForegroundColor = "Yellow"
"Please note that special character should be escaped. For example, $ should be \$"
[Console]::ResetColor()
$adUserPassword = GetInput -prompt 'Your AD user password' -IsPassword $true
"-----"

#$csvFile = Read-Host 'Csv File '
$csvFile = '.\CloneVMs.csv'

#----- Main Script -----

#Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))
{
    Write-Host 'Exit since failed to login vCenter'
    exit
}
else

```

```

{
  Write-Host 'vCenter is connected'
}

#Read input CSV file
$csvData = Import-CSV $csvFile

$destFolder = "/home/$guestUser/"

#Handle VMs one by one
foreach ($line in $csvData)
{
  "-----"
  $VMName = $line.VMName
  write-host -ForegroundColor Yellow "VM: $VMName`n"

  $cmd = "sudo /usr/bin/net ads join -U $adUser%$adUserPassword"
  Write-Host "Run cmd 'sudo /usr/bin/net ads join' in VM '$VMName' with user '$guestUser'"
  RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd
}

Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

## Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\ClonedVMs_JoinDomain_SSH.ps1
-----
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
-----
Your VM guest OS user name: ViewUser
Your VM guest OS user password: *****
-----
Type the AD user name to join the AD: viewadmin
Please type the AD user password.
Please note that special character should be escaped. For example, $ should be \$
Your AD user password: *****

```

## Sample Script to Upload Configuration Files to Linux Virtual Machines

You can customize and use the following sample script to upload the configuration files `config` and `viewagent-custom.conf` to multiple Linux virtual machines (VMs).

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at [https://www.vmware.com/support/pubs/view\\_pubs.html](https://www.vmware.com/support/pubs/view_pubs.html).

## Script Input

This script reads one input file, which is described in [“Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops,”](#) on page 69. This script also interactively asks for the following information:

- IP address of the vCenter Server

- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- Administrator login name for the ESXi host
- Administrator password for the ESXi host
- User login name for the Linux VM
- User password for the Linux VM

## Script Content

```
<#
Upload the configuration files config and viewagent-custom.conf to Linux VMs
#>
#----- Functions -----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}

#----- Handle Input -----
"-----"
write-host -ForegroundColor Blue 'Please ensure your config file and viewagent-custom.conf file
are in current working directory'
$vcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$vcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$vcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$hostAdmin = GetInput -prompt 'Your ESXi host admin user name, such as root' -IsPassword $false
$hostPassword = GetInput -prompt "Your ESXi admin user password" -IsPassword $true
"-----"
$guestUser = GetInput -prompt 'Your VM guest OS user name' -IsPassword $false
$guestPassword = GetInput -prompt 'Your VM guest OS user password' -IsPassword $true
"-----"

$csvFile = '.\CloneVMs.csv'
$setConfig = $false
$setCustomConf = $false
```



```

$config_File = "config"
$customConf_File = "viewagent-custom.conf"

#check if config file exists
if(Test-Path $config_File)
{
    $setConfig = $true
    write-host -ForegroundColor Yellow "config" file found'
}
else
{
    write-host -ForegroundColor Yellow "config" file not found, skip it'
}

if(Test-Path $customConf_File)
{
    $setCustomConf = $true
    write-host -ForegroundColor Yellow "viewagent-custom.conf" file found'
}
else
{
    write-host -ForegroundColor Yellow "viewagent-custom.conf" file not found, skip it'
}

if (($setConfig -eq $false)-AND ($setCustomConf -eq $false))
{
    write-host -ForegroundColor Red 'Both file not found, exit'
    exit
}

#Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))
{
    Write-Host 'Exit since failed to login vCenter'
    exit
}
else
{
    Write-Host 'vCenter is connected'
}

#Read input CSV file
$csvData = Import-CSV $csvFile

$destFolder = "/home/$guestUser/"

#Handle VMs one by one
foreach ($line in $csvData)
{
    "`n-----"
    $VMName = $line.VMName
    write-host -ForegroundColor Yellow "VM: $VMName`n"
}

```

```

#Try to delete the configuration file from home folder on destination VM
$cmd = "rm -rf config viewagent-custom.conf"
Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

if ($setConfig)
{
Write-Host "Upload File '$config_File' to '$destFolder' of VM '$VMName' with user
'$guestUser'"
Copy-VMGuestFile -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -LocalToGuest -Destination $destFolder -
Source $config_File

$cmd = "sudo mv ./ $config_File /etc/vmware/";
Write-Host "Move configuraton file: $cmd"
Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd
}

if ($setCustomConf)
{
Write-Host "Upload File '$customConf_File' to '$destFolder' of VM '$VMName' with user
'$guestUser'"
Copy-VMGuestFile -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -LocalToGuest -Destination $destFolder -
Source $customConf_File

$cmd = "sudo mv ./ $customConf_File /etc/vmware/";
Write-Host "Move configuraton file: $cmd"
Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
$guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd
}
}
Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

## Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\UpdateOptionFile.ps1
-----
Please ensure your config file and view-agent.conf file are in current working directory.
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
-----
Your ESXi host admin user name, such as root: root
Your ESXi host admin user password: *****
-----
Your VM guest OS user name: ViewUser
Your VM guest OS user password: *****

```

## Sample Script to Upload Configuration Files to Linux Virtual Machines Using SSH

You can customize and use the following sample script to upload the configuration files `config` and `viewagent-custom.conf` to multiple Linux virtual machines (VMs). This script uses SSH to run commands on the Linux VMs.

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at [https://www.vmware.com/support/pubs/view\\_pubs.html](https://www.vmware.com/support/pubs/view_pubs.html).

### Script Input

This script reads one input file, which is described in “[Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#),” on page 69. This script also interactively asks for the following information:

- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- User login name for the Linux VM
- User password for the Linux VM

### Script Content

```
<#
Upload the configuration files config and viewagent-custom.conf to Linux VMs using SSH
#>
#----- Functions -----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}
function Check_SSH_Client
{
    Param($IsPlink, $IsPSCP)
    if ($IsPlink)
    {
```

```

        if (Test-Path ".\plink.exe")
        {
            write-host -ForegroundColor Yellow 'SSH client "plink.exe" found'
        }
        else
        {
            write-host -ForegroundColor Red 'SSH client "plink.exe" not found, please download
from its official web site'
            exit
        }
    }
    if ($IsPSCP)
    {
        if (Test-Path ".\pscp.exe")
        {
            write-host -ForegroundColor Yellow 'SSH client "pscp.exe" found'
        }
        else
        {
            write-host -ForegroundColor Red 'SSH client "pscp.exe" not found, please download
from its official web site'
            exit
        }
    }
}

function RunCmdViaSSH
{
    Param($VM_Name, $User, $Password, $Cmd, $returnOutput = $false)

    $VM= Get-VM $VM_Name
    $IP = $VM.guest.IPAddress[0]
    write-host "Run cmd on $VM_Name ($IP)"
    if($returnOutput)
    {
        $command = "echo yes | .\plink.exe -ssh -l $user -pw $password $IP " + "'" + $cmd + "'"
        $output = Invoke-Expression $command
        return $output
    }
    else
    {
        {
            echo yes | .\plink.exe -ssh -l $user -pw $password $IP "$cmd"
        }
    }
}

function UploadFileViaSSH
{
    Param($VM_Name, $User, $Password, $LocalPath, $DestPath)

    $VM= Get-VM $VM_Name
    $IP = $VM.guest.IPAddress[0]
    $command = "echo yes | .\pscp.exe -l $User -pw $Password $LocalPath $IP" + ":" + "$DestPath"
    write-host "Upload file: $command"
    Invoke-Expression $command
}

```

```

}

#----- Handle Input -----
"-----"
Check_SSH_Client -IsPlink $true -IsPSCP $true
"-----"
write-host -ForegroundColor Blue 'Please ensure your config file and viewagent-custom.conf file
are in current working directory'
$vcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$vcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$vcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$guestUser = GetInput -prompt 'Your VM guest OS user name' -IsPassword $false
$guestPassword = GetInput -prompt 'Your VM guest OS user password' -IsPassword $true
"-----"

$csvFile = '.\CloneVMs.csv'
$setConfig = $false
$setCustomConf = $false
$config_File = "config"
$customConf_File = "viewagent-custom.conf"

#check if config file exists
if(Test-Path $config_File)
{
    $setConfig = $true
    write-host -ForegroundColor Yellow '"config" file found'
}
else
{
    write-host -ForegroundColor Yellow '"config" file not found, skip it'
}

if(Test-Path $customConf_File)
{
    $setCustomConf = $true
    write-host -ForegroundColor Yellow '"viewagent-custom.conf" file found'
}
else
{
    write-host -ForegroundColor Yellow '"viewagent-custom.conf" file not found, skip it'
}

if (($setConfig -eq $false)-AND ($setCustomConf -eq $false))
{
    write-host -ForegroundColor Red 'Both file not found, exit'
    exit
}

#Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))
{
    Write-Host 'Exit since failed to login vCenter'
    exit
}

```

```

}
else
{
    Write-Host 'vCenter is connected'
}

#Read input CSV file
$csvData = Import-CSV $csvFile

$destFolder = "/home/$guestUser/"

#Handle VMs one by one
foreach ($line in $csvData)
{
    "`n-----"
    $VMName = $line.VMName
    write-host -ForegroundColor Yellow "VM: $VMName`n"

    #Try to delete the configuration file from home folder on destination VM
    $cmd = "rm -rf config viewagent-custom.conf"
    Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
    RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd

    if ($setConfig)
    {
        Write-Host "Upload File '$config_File' to '$destFolder' of VM '$VMName' with user '$guestUser'"
        UploadFileViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -LocalPath $config_File -DestPath $destFolder

        $cmd = "sudo mv ./ $config_File /etc/vmware/";
        Write-Host "Move configuraton file: $cmd"
        RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd
    }

    if ($setCustomConf)
    {
        Write-Host "Upload File '$customConf_File' to '$destFolder' of VM '$VMName' with user '$guestUser'"
        UploadFileViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -LocalPath $customConf_File -DestPath $destFolder

        $cmd = "sudo mv ./ $customConf_File /etc/vmware/";
        Write-Host "Move configuraton file: $cmd"
        RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd
    }
}
Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

## Script Execution

The following messages are from an execution of the script:

```
PowerCLI C:\scripts> .\UpdateOptionFile.ps1
-----
Please ensure your config file and view-agent.conf file are in current working directory.
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
-----
Your VM guest OS user name: ViewUser
Your VM guest OS user password: *****
```

## Sample Script to Upgrade Horizon Agent on Linux Desktop Machines

You can customize and use the following sample script to upgrade Horizon Agent on multiple Linux virtual machines (VMs).

This script uploads the installer tar ball to each VM before installing Horizon Agent. The upload task can be time-consuming, especially when a large number of VMs is involved and the network speed is slow. To save time, you can run the script that uses SSH, or put the installer tar ball in a shared location that is available to each VM so that uploading the file is not necessary.

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at [https://www.vmware.com/support/pubs/view\\_pubs.html](https://www.vmware.com/support/pubs/view_pubs.html).

## Script Input

This script reads one input file, which is described in “[Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#),” on page 69. This script also interactively asks for the following information:

- Acceptance of Horizon Agent EULA (end user license agreement)
- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- Administrator login name for the ESXi host
- Administrator password for the ESXi host
- User login name for the Linux guest operating system
- User password for the Linux guest operating system
- Horizon Agent tar ball path
- Upgrade to managed VM
- Install the Smartcard redirection feature

## Script Content

```
<#
Upload the Linux Agent installer tar ball and re-install
#>

#-----
Functions-----
```

```

function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}
#-----Handle
input-----
"-----"
$acceptEULA = GetInput -prompt 'Accept Linux View Agent EULA in tar bundle ("yes" or "no")' -
IsPassword $false
if ($acceptEULA -ne "yes")
{
    write-host -ForegroundColor Red "You need accept the EULA with 'yes'(case sensitive)"
    exit
}
$svcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$svcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$svcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$hostAdmin = GetInput -prompt 'Your ESXi host admin user name, such as root' -IsPassword $false
$hostPassword = GetInput -prompt "Your ESXi admin user password" -IsPassword $true
"-----"
$guestUser = GetInput -prompt 'Your VM guest OS user name' -IsPassword $false
$guestPassword = GetInput -prompt 'Your VM guest OS user password' -IsPassword $true
"-----"
$agentInstaller = GetInput -prompt 'Type the View Agent tar ball path' -IsPassword $false
"-----"
$UpgradeToManagedVM = GetInput -prompt 'Upgrade to managed VM ("yes" or "no")' -IsPassword $false
if (($UpgradeToManagedVM -ne "yes") -AND $UpgradeToManagedVM -ne "no")
{
    write-host -ForegroundColor Red "You need select 'yes' or 'no'(case sensitive)"
    exit
}
$installSmartcard = GetInput -prompt 'Install the Smartcard redirection feature ("yes" or "no")'
-IsPassword $false
if (($installSmartcard -ne "yes") -AND $installSmartcard -ne "no")
{
    write-host -ForegroundColor Red "You need select 'yes' or 'no'(case sensitive)"
    exit
}

```



```

}
"-----"

# $csvFile = Read-Host 'Csv File '
$csvFile = '.\CloneVMs.csv'

# check if file exists
if (!(Test-Path $agentInstaller))
{
write-host -ForegroundColor Red "installer File not found"
exit
}

# check if file exists
if (!(Test-Path $csvFile))
{
write-host -ForegroundColor Red "CSV File not found"
exit
}
#-----
Functions-----
function GetSourceInstallerMD5()
{
    $agentInstallerPath = Convert-Path $agentInstaller;
    $md5 = New-Object -TypeName System.Security.Cryptography.MD5CryptoServiceProvider;
    $md5HashWithFormat =
[System.BitConverter]::ToString($md5.ComputeHash([System.IO.File]::ReadAllBytes($agentInstallerPa
th)));
    $md5Hash = ($md5HashWithFormat.replace("-", "")).ToLower();
    return $md5Hash;
}

#-----
Main-----
# Get installer MD5Sum
$installerMD5Hash = GetSourceInstallerMD5;

# Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))
{
    Write-Host 'Exit since failed to login vCenter'
    exit
}
else
{
    Write-Host 'vCenter is connected'
}

# Read input CSV file
$csvData = Import-CSV $csvFile

$destFolder = "/home/$guestUser/"

# Handle VMs one by one

```

```

foreach ($line in $csvData)
{
    "`n-----"
    $VMName = $line.VMName
    write-host -ForegroundColor Yellow "VM: $VMName`n"

    $cmd = "rm -rf VMware-*linux-*"
    Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
    Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
    $guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

    #Upload installer tar ball to Linux VM
    Write-Host "Upload File '$agentInstaller' to '$destFolder' of VM '$VMName' with user
    '$guestUser'"
    Copy-VMGuestFile -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
    $guestUser -GuestPassword $guestPassword -Confirm:$false -LocalToGuest -Destination $destFolder -
    Source $agentInstaller

    #Check the uploaded installer md5sum
    $cmd = "md5sum VMware-*linux-*"
    Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
    $output = Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -
    GuestUser $guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText
    $cmd

    if($output.Contains($installerMD5Hash))
    {
        Write-Host $VMName": Uploaded installer's MD5Sum matches the local installer's MD5Sum";
        Write-Host $VMName": Extract the installer and do installation";
        $cmd = "tar -xzvf VMware-*linux-*.tar.gz"
        Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
        Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
        $guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

        $cmd = "sudo setenforce 0";
        Write-Host "Set the selinux to permissive mode: $cmd"
        Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
        $guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

        $cmd = "sudo killall /usr/lib/vmware/viewagent/VMwareBlastServer/VMwareBlastServer"
        Write-Host "Stop VMwareBlastServer before upgrading: $cmd"
        Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
        $guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

        #Run the upgrade command.
        $cmd = "cd VMware-*linux-* && sudo ./install_viewagent.sh -A yes -m $installSmartcard -
        M $UpgradeToManagedVM"
        Write-Host "Run upgrade cmd in VM '$VMName' with user '$guestUser': $cmd"
        Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
        $guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd

        $cmd = "sudo shutdown -r +1&"
        Write-Host "Reboot to apply the View Agent installation"
        Invoke-VMScript -HostUser $hostAdmin -HostPassword $hostPassword -VM $VMName -GuestUser
        $guestUser -GuestPassword $guestPassword -Confirm:$false -ScriptType Bash -ScriptText $cmd
    }
}

```

```

    }
    else
    {
        Write-Host $VMName": Uploaded installer's MD5Sum does NOT match the local installer's
MD5Sum";
        Write-Host $VMName": Skip the installation. Please check your network and VMware Tools
status";
        exit;
    }
}
Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

## Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\InstallAgent.ps1
-----
Accept Linux Horizon Agent EULA in tar bundle ("yes" or "no"): yes
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
-----
Your ESXi host admin user name, such as root: root
Your ESXi host admin user password: *****
-----
Your VM guest OS user name: ViewUser
Your VM guest OS user password: *****
-----
Type the Horizon Agent tar ball path. Please take care of the installer arch: .\VMware-viewagent-
linux-x86_64-x.y.z-1234567.tar.gz
-----
-----
Upgrade to managed VM ("yes" or "no"): yes
Install the Smartcard redirection feature ("yes" or "no"): no

```

## Sample Script to Upgrade Horizon Agent on Linux Virtual Machines Using SSH

You can customize and use the following sample script to upgrade Horizon Agent on multiple Linux virtual machines (VMs). This script uses SSH to run commands on the Linux VMs.

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at [https://www.vmware.com/support/pubs/view\\_pubs.html](https://www.vmware.com/support/pubs/view_pubs.html).

### Script Input

This script reads one input file, which is described in [“Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops,”](#) on page 69. This script also interactively asks for the following information:

- Acceptance of Horizon Agent EULA (end user license agreement)
- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server

- Administrator login name for the ESXi host
- Administrator password for the ESXi host
- User login name for the Linux guest operating system
- User password for the Linux guest operating system
- Horizon Agent tar ball path
- Upgrade to managed VM
- Install the Smartcard redirection feature

## Script Content

```

<#
Upload the Linux Agent installer tar ball and re-install
#>

#-----
Functions-----
function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {
        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}
function Check_SSH_Client
{
    Param($IsPlink, $IsPSCP)
    if ($IsPlink)
    {
        if (Test-Path ".\plink.exe")
        {
            write-host -ForegroundColor Yellow 'SSH client "plink.exe" found'
        }
        else
        {
            write-host -ForegroundColor Red 'SSH client "plink.exe" not found, please download
from its official web site'
            exit
        }
    }
}

```

```

}
if ($IsPSCP)
{
    if (Test-Path ".\pscp.exe")
    {
        write-host -ForegroundColor Yellow 'SSH client "pscp.exe" found'
    }
    else
    {
        write-host -ForegroundColor Red 'SSH client "pscp.exe" not found, please download
from its official web site'
        exit
    }
}
}

function RunCmdViaSSH
{
    Param($VM_Name, $User, $Password, $Cmd, $returnOutput = $false)

    $VM= Get-VM $VM_Name
    $IP = $VM.guest.IPAddress[0]
    write-host "Run cmd on $VM_Name ($IP)"
    if($returnOutput)
    {
        $command = "echo yes | .\plink.exe -ssh -l $user -pw $password $IP " + "'" + $cmd + "'"
        $output = Invoke-Expression $command
        return $output
    }
    else
    {
        echo yes | .\plink.exe -ssh -l $user -pw $password $IP "$cmd"
    }
}

function UploadFileViaSSH
{
    Param($VM_Name, $User, $Password, $LocalPath, $DestPath)

    $VM= Get-VM $VM_Name
    $IP = $VM.guest.IPAddress[0]
    $command = "echo yes | .\pscp.exe -l $User -pw $Password $LocalPath $IP" + ":" + "$DestPath"
    write-host "Upload file $LocalPath to VM $VM_Name with user $User"
    Invoke-Expression $command
}

#-----Handle
input-----
"-----"
Check_SSH_Client -IsPlink $true -IsPSCP $true
"-----"
$acceptEULA = GetInput -prompt 'Accept Linux View Agent EULA in tar bundle ("yes" or "no")' -
IsPassword $false
if ($acceptEULA -ne "yes")

```

```

{
    write-host -ForegroundColor Red "You need accept the EULA with 'yes'(case sensitive)"
    exit
}
$SvcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$SvcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$SvcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$guestUser = GetInput -prompt 'Your VM guest OS user name' -IsPassword $false
$guestPassword = GetInput -prompt 'Your VM guest OS user password' -IsPassword $true
"-----"
$agentInstaller = GetInput -prompt 'Type the View Agent tar ball path' -IsPassword $false
"-----"
$UpgradeToManagedVM = GetInput -prompt 'Upgrade to managed VM ("yes" or "no")' -IsPassword $false
if (($UpgradeToManagedVM -ne "yes") -AND $UpgradeToManagedVM -ne "no")
{
    write-host -ForegroundColor Red "You need select 'yes' or 'no'(case sensitive)"
    exit
}
$installSmartcard = GetInput -prompt 'Install the Smartcard redirection feature ("yes" or "no")'
-IsPassword $false
if (($installSmartcard -ne "yes") -AND $installSmartcard -ne "no")
{
    write-host -ForegroundColor Red "You need select 'yes' or 'no'(case sensitive)"
    exit
}
}
"-----"

#$csvFile = Read-Host 'Csv File '
$csvFile = '.\CloneVMs.csv'

#check if file exists
if (!(Test-Path $agentInstaller))
{
    write-host -ForegroundColor Red "installer File not found"
    exit
}

#check if file exists
if (!(Test-Path $csvFile))
{
    write-host -ForegroundColor Red "CSV File not found"
    exit
}
}
#-----
Functions-----
function GetSourceInstallerMD5()
{
    $agentInstallerPath = Convert-Path $agentInstaller;
    $md5 = New-Object -TypeName System.Security.Cryptography.MD5CryptoServiceProvider;
    $md5HashWithFormat =
[System.BitConverter]::ToString($md5.ComputeHash([System.IO.File]::ReadAllBytes($agentInstallerPa
th)));
    $md5Hash = ($md5HashWithFormat.replace("-", "")).ToLower();
    return $md5Hash;
}

```

```

}

#-----
Main-----
#Get installer MD5Sum
$installerMD5Hash = GetSourceInstallerMD5;

#Connect to vCenter
$VC_Conn_State = Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
if([string]::IsNullOrEmpty($VC_Conn_State))
{
    Write-Host 'Exit since failed to login vCenter'
    exit
}
else
{
    Write-Host 'vCenter is connected'
}

#Read input CSV file
$csvData = Import-CSV $csvFile

$destFolder = "/home/$guestUser/"

#Handle VMs one by one
foreach ($line in $csvData)
{
    "`n-----"
    $VMName = $line.VMName
    write-host -ForegroundColor Yellow "VM: $VMName`n"

    $cmd = "rm -rf VMware-*linux-*"
    Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
    RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd

    #Upload installer tar ball to Linux VM
    Write-Host "Upload File '$agentInstaller' to '$destFolder' of VM '$VMName' with user '$guestUser'"
    UploadFileViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -LocalPath $agentInstaller -DestPath $destFolder

    #Check the uploaded installer md5sum
    $cmd = "md5sum VMware-*linux-*"
    Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
    $output = RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd -
    $returnOutput $true

    if($output.Contains($installerMD5Hash))
    {
        Write-Host $VMName": Uploaded installer's MD5Sum matches the local installer's MD5Sum";
        Write-Host $VMName": Extract the installer and do installation";

        $cmd = "tar -xzf VMware-*linux-*.tar.gz"
        Write-Host "Run cmd '$cmd' in VM '$VMName' with user '$guestUser'"
    }
}

```

```

RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd

$cmd = "sudo setenforce 0";
Write-Host "Set the selinux to permissive mode: $cmd"
RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd

$cmd = "sudo killall /usr/lib/vmware/viewagent/VMwareBlastServer/VMwareBlastServer"
Write-Host "Stop VMwareBlastServer before upgrading: $cmd"
RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd

#Run the upgrade command.
$cmd = "cd VMware-*--linux-* && sudo ./install_viewagent.sh -r yes -A yes -m
$installSmartcard -M $UpgradeToManagedVM"
Write-Host "Run upgrade cmd in VM '$VMName' with user '$guestUser': $cmd"
RunCmdViaSSH -VM_Name $VMName -User $guestUser -Password $guestPassword -Cmd $cmd
Write-Host -ForegroundColor Yellow "Linux Agent installer will reboot the Linux VM after
upgrade, and you may hit the ssh connection closed error message, which is expectation"
}
else
{
Write-Host $VMName": Uploaded installer's MD5Sum does NOT match the local installer's
MD5Sum";
Write-Host $VMName": Skip the installation. Please check your network and VMware Tools
status";
exit;
}
}
Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

## Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\InstallAgent.ps1
-----
Accept Linux Horizon Agent EULA in tar bundle ("yes" or "no"): yes
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
-----
Your VM guest OS user name: ViewUser
Your VM guest OS user password: *****
-----
Type the Horizon Agent tar ball path. Please take care of the installer arch: .\VMware-viewagent-
linux-x86_64-x.y.z-1234567.tar.gz
-----
Upgrade to managed VM ("yes" or "no"): yes
Install the Smartcard redirection feature ("yes" or "no"): no

```



## Sample Script to Perform Operations on Linux Virtual Machines

You can customize and use the following sample script to perform operations on multiple Linux virtual machines (VMs). The operations include powering on, powering off, shutting down, restarting, and deleting the VMs.

This script can delete virtual machines from vCenter Server but not from View.

To copy and paste the script content without page breaks, use the HTML version of this topic, available from the Horizon 7 documentation page at [https://www.vmware.com/support/pubs/view\\_pubs.html](https://www.vmware.com/support/pubs/view_pubs.html).

### Script Input

This script reads one input file, which is described in “[Input File for the Sample PowerCLI Scripts to Deploy Linux Desktops](#),” on page 69. This script also interactively asks for the following information:

- IP address of the vCenter Server
- Administrator login name for the vCenter Server
- Administrator password for the vCenter Server
- Action to perform, which can be power-on, power-off, shut down guest, restart VM, restart VM guest, or delete VM.
- The wait time, in seconds, between operations on the VMs.

### Script Content

```
<#
.DESCRIPTION
The Tool supports:
1. Power off VMs
2. Power on VMs
3. Shutdown VMs
4. Restart VMs
5. Restart VM guest
6. Delete VMs from Disk
.NOTES
#>

#----- Functions -----

function GetInput
{
    Param($prompt, $IsPassword = $false)
    $prompt = $prompt + ": "
    Write-Host $prompt -NoNewLine
    [Console]::ForegroundColor = "Blue"
    if ($IsPassword)
    {
        $input = Read-Host -AsSecureString
        $input =
[Runtime.InteropServices.Marshal]::PtrToStringAuto([Runtime.InteropServices.Marshal]::SecureStringToBSTR($input))
    }
    else
    {

```

```

        $input = Read-Host
    }

    [Console]::ResetColor()
    return $input
}

function IsVMExists ($VMExists)
{
    Write-Host "Checking if the VM $VMExists Exists"
    [bool]$Exists = $false

    #Get all VMS and check if the VMS is already present in VC
    $listvm = Get-vm
    foreach ($lvm in $listvm)
    {
        if($VMExists -eq $lvm.Name )
        {
            $Exists = $true
            Write-Host "$VMExists is Exist"
        }
    }
    return $Exists
}

function Delete_VM($VMToDelete)
{
    Write-Host "Deleting VM $VMToDelete"
    Get-VM $VMToDelete | where { $_.PowerState -eq "PoweredOn" } | Stop-VM -confirm:$false
    Get-VM $VMToDelete | Remove-VM -DeleteFromDisk -confirm:$false
}

#----- Handle input -----
"-----"
$svcAddress = GetInput -prompt "Your vCenter address" -IsPassword $false
$svcAdmin = GetInput -prompt "Your vCenter admin user name" -IsPassword $false
$svcPassword = GetInput -prompt "Your vCenter admin user password" -IsPassword $true
"-----"
$action = GetInput -prompt 'Select action: 1). Power On 2). Power Off 3) Shutdown VM Guest 4).
Restart VM 5). Restart VM Guest 6). Delete VM' -IsPassword $false
$sleepTime = GetInput -prompt 'Wait time (seconds) between each VM' -IsPassword $false
"-----"
[Console]::ForegroundColor = "Yellow"
switch ($action)
{
    1
    {
        "Your selection is 1). Power On"
    }
    2
    {
        "Your selection is 2). Power Off"
    }
    3
    {

```

```

    "Your selection is 3) Shutdown"
}
4
{
    "Your selection is 4). Restart VM"
}
5
{
    "Your selection is 5). Restart VM Guest"
}
6
{
    "Your selection is 6). Delete VM"
}
default
{
    "Invalid selection for action: $action"
    exit
}
}
[Console]::ResetColor()
$csvFile = '.\CloneVMs.csv'

#check if file exists
if (!(Test-Path $csvFile))
{
    write-host -ForegroundColor Red "CSV File not found"
    exit
}
"-----"

#----- Main -----
#Read input CSV file
Disconnect-VIServer $vcAddress -Confirm:$false
#Connect-VIServer $vcAddress -ErrorAction Stop -user $vcAdmin -password $vcPassword
Connect-VIServer $vcAddress -user $vcAdmin -password $vcPassword
$csvData = Import-CSV $csvFile

foreach ($line in $csvData)
{
    $VMName = $line.VMName
    switch ($action)
    {
        1
        {
            Get-VM $VMName | Start-VM -Confirm:$false
        }
        2
        {
            Get-VM $VMName | Stop-VM -Confirm:$false
        }
        3
        {
            Get-VM $VMName | Shutdown-VMGuest -Confirm:$false
        }
    }
}

```

```

4
{
  Get-VM $VMName | Restart-VM -Confirm:$false
}
5
{
  Get-VM $VMName | Restart-VMGuest -Confirm:$false
}
6
{
  if (IsVMExists ($VMName))
  {
    Delete_VM ($VMName)
  }
}
default{}
}
Start-Sleep -s $sleepTime
}

Disconnect-VIServer $vcAddress -Confirm:$false
exit

```

## Script Execution

The following messages are from an execution of the script:

```

PowerCLI C:\scripts> .\VMOperations.ps1
Your vCenter address: 10.117.44.17
Your vCenter admin user name: administrator
Your vCenter admin user password: *****
-----
Select action: 1). Power On 2). Power Off 3) Shutdown VM Guest 4). Restart VM 5). Restart VM
Guest 6). Delete VM: 1
Wait time (seconds) between each VM: 20
-----
Your selection is 6). Delete VM

```

For the operations power on, restart VM, and restart VM guest, specify a wait time between virtual machines of at least 20 seconds to avoid a boot storm situation, which might cause some operations to fail.

# Troubleshooting Linux Desktops

---

Certain issues might arise when you manage Linux desktops. You can follow various procedures to diagnose and fix problems.

This chapter includes the following topics:

- [“Collect Diagnostic Information for Horizon 7 for Linux Machine,”](#) on page 101
- [“Troubleshooting Copy and Paste between Remote Desktop and Client Host,”](#) on page 102
- [“Configuring the Linux Firewall to Allow Incoming TCP Connections,”](#) on page 102
- [“View Agent Fails to Disconnect on an iPad Pro Horizon Client,”](#) on page 102
- [“SLES 12 SP1 Desktop does not Auto Refresh after Drag and Drop,”](#) on page 103
- [“SSO Fails to Connect to a PowerOff Agent,”](#) on page 103
- [“Unreachable VM After Creating a Manual Desktop Pool for Linux,”](#) on page 103

## Collect Diagnostic Information for Horizon 7 for Linux Machine

You can collect diagnostic information to help VMware Technical Support diagnose and resolve issues with a Horizon 7 for Linux machine. You create a Data Collection Tool (DCT) bundle that gathers the machine's configuration information and logs into a compressed tarball.

### Procedure

- 1 Log in to the Linux virtual machine as a user with the required privileges.
- 2 Open a command prompt and run the `dct-debug.sh` script.

```
sudo /usr/lib/vmware/viewagent/bin/dct-debug.sh
```

The script generates a tarball that contains the DCT bundle. For example:

```
ubuntu-12-vdm-sdct-20150201-0606-agent.tgz
```

The tarball is generated in the directory from which the script was executed (the current working directory).

## Troubleshooting Copy and Paste between Remote Desktop and Client Host

Copy and Paste between the remote desktop and client host takes more than three seconds for maximum supported data of 1 MB. This issue does not occur if you copy and paste a small data size.

### Problem

When you configure 1 vCPU and 1 GB memory for SLED 11 SP3/SP4 desktop, it might take more than three seconds to copy and paste between the remote desktop and local client host.

### Cause

The delay in copy and paste might occur due to the old operating system APIs of SLED 11 SP3/SP4.

### Solution

- ◆ Configure two vCPUs and 2 GB memory for SLED 11 SP3/SP4.

## Configuring the Linux Firewall to Allow Incoming TCP Connections

To allow users to connect to their Linux desktops, the desktops must be able to accept incoming TCP connections from Horizon Client devices, security server, and View Connection Server.

On Ubuntu and Kylin distributions, the `iptables` firewall is configured by default with an input policy of `ACCEPT`.

On RHEL and CentOS distributions, where possible, the Horizon Agent installer script configures the `iptables` firewall with an input policy of `ACCEPT`.

Make sure that `iptables` on a RHEL or CentOS guest operating system has an input policy of `ACCEPT` for new connections from the Blast port, 22443.

When the BSG is enabled, client connections are directed from a Horizon Client device through the BSG on a security server or View Connection Server to the Linux desktop. When the BSG is not enabled, connections are made directly from the Horizon Client device to the Linux desktop.

## View Agent Fails to Disconnect on an iPad Pro Horizon Client

The SUSE View Agent connection fails to disconnect after a restart or shutdown on a iPad Pro Horizon Client.

### Problem

When you restart or shutdown a SUSE virtual machine on an iPad Pro Horizon Client, the desktop does not respond. The View Agent fails to disconnect.

### Cause

SUSE machine might not be sending messages correctly to Horizon Client after a restart or shutdown operation.

### Solution

- ◆ Disconnect the desktop connection manually from iPad Pro Horizon Client.

## SLES 12 SP1 Desktop does not Auto Refresh after Drag and Drop

SLES 12 SP1 does not auto refresh in a multimon mode when you drag and drop a gnome terminal.

### Problem

When you launch SLES 12 SP1 in a multimon mode and return to the window mode, the desktop does not refresh automatically when you drag and drop a gnome terminal.

### Cause

The gnome terminal does not respond to the drag and drop operation.

### Solution

- 1 End the gnome-shell.
  - ◆ `kill -9 `pidof gnome-shell``
- 2 Restart gnome-shell again.

## SSO Fails to Connect to a PowerOff Agent

SSO does not connect to a poweroff agent.

### Problem

When you login as a broker and connect to an agent, SSO fails to connect to the poweroff agent.

### Solution

- ◆ Manually login to the desktop or disconnect and reconnect to the agent again.

## Unreachable VM After Creating a Manual Desktop Pool for Linux

The virtual machine state is not responding.

### Problem

The virtual machine status might be Waiting for Agent or Unreachable after you create a Manual Desktop Pool.

### Cause

There might be several user error configuration or setup causes for the virtual machine state to be Unreachable or Waiting for Agent.

- Verify that the option `machine.id` exists in the virtual machines vmx configuration file.
 

If it does not exist, then verify that the virtual machine was added to the desktop pool correctly. Else recreate the desktop pool to let the broker rewrite the option to the vmx configuration file.
- Verify that the VMware Tool or Open VM Tool is installed correctly.
 

If the steps to install VMware Tool or Open VM Tool were not performed correctly, the `vmware-rpctool` command might not exist under `PATH` in the Linux virtual machine. You must follow the guide to install VMware Tool or Open VM Tool.

Run the command after you finish installing.

```
#vmware-rpctool "machine.id.get"
```

The `machine.id` values are listed from the virtual machines vmx configuration file.

- Verify if the FQDN of the broker can be resolved to the IP Address in the agent Linux virtual machine.





# Index

## A

Active Directory, integrating with Linux **25**  
automated full-clone desktop pool creation, Linux virtual machines **59**

## B

broker powercli **61**  
bulk deployment  
    create a virtual machine template for cloning **67**  
    input file for sample scripts **69**  
    overview **65**  
bulk upgrade **67**

## C

configuration options  
    audio out **47**  
    clipboard redirection **47**  
    example Blast settings for Linux desktops) **54**  
    example client drive redirection for Linux desktops **55**  
    left-handed mouse **47**  
    lossless PNG mode **47**  
    single sign-on (SSO) **47**  
configuring **43**

## D

desktop pool creation, Linux virtual machines **57**  
DIGEST-MD5 **41**

## F

firewalls, Linux desktops **102**

## G

glossary **5**  
graphics **29**

## H

Horizon 7 for Linux, bulk deployment **65**  
Horizon Agent  
    installing on a Linux virtual machine **41**  
    Linux installation command options **42**  
    upgrading on a Linux virtual machine **45**

## I

install\_viewagent.sh, command usage and options **42**

installing **22**  
intended audience **5**

## K

Kerberos **41**

## L

Linux desktops  
    configuring **47**  
    creating and managing Linux desktop pools **57**  
    features **7**  
    features and requirements **7**  
    installing Horizon Agent **41**  
    setting up AD integration **25**  
Linux systems  
    adding to automated desktop pools **59**  
    adding to desktop pools **57**  
    collecting diagnostic information **101**  
    configuring the firewall **102**  
    desktops **5**  
    overview of desktop setup steps **10**  
    preparing for desktop use **20**  
    vSphere console display **55**  
Linux virtual machines, preparing for desktop deployment **19**

## M

managing manual desktop **58**

## N

NVIDIA display driver, verify the installation **33, 37**  
NVIDIA display driver for vDGA, installing **35**  
NVIDIA GRID vGPU  
    installing the VIB for Linux desktops **30**  
    virtual GPU Types **31**  
NVIDIA GRID vGPU display driver, installing **32**  
NVIDIA vGPU, configuring a shared PCI device **31**

## O

OpenLDAP **25**

## R

RHEL  
    configuring for vDGA **34**

configuring for vGPU **29**

configuring for vSGA **37**

## **S**

sample script

clone desktop machines using SSH **76**

perform operations on VMs **97**

to clone desktop machines **69, 73**

to upgrade Horizon Agent **87**

upgrade Horizon Agent using SSH **91**

upload configuration files **79**

upload configuration files using SSH **83**

sample scripts, input file **69**

single sign-on **26**

smart card redirection **26**

sso failure **103**

SSSD LDAP Authentication **25**

## **T**

troubleshooting **101–103**

troubleshooting, disconnecting **102**

## **U**

uninstalling **46**

unreachable VM **103**

## **V**

vDGA

adding PCI device to a Linux machine **35**

enabling DirectPath I/O on a host **34**

vDGA (Virtual Dedicated Graphics Acceleration),  
for RHEL 6 **34**

vGPU, configuring supported RHEL  
distributions **29**

View Agent, Linux operating system  
requirements **11**

virtual machines, creating for Linux desktops **19**

VMware Tools, configuring on a Linux guest **20**

vSGA

configuring 3D settings on a Linux video  
card **38**

for RHEL 7 **37**

installing the VIB for Linux desktops **37**

verify on a Linux machine **39**

vSphere console, suppress display **55**

## **W**

Winbind **25**